

(12) **United States Patent**
Stevens et al.

(10) **Patent No.:** US 9,372,820 B2
(45) **Date of Patent:** *Jun. 21, 2016

(54) **NETWORK RESOURCE MANAGEMENT SYSTEM UTILIZING PHYSICAL NETWORK IDENTIFICATION FOR BRIDGING OPERATIONS**

(71) Applicant: **International Business Machines Corporation**, Armonk, NY (US)

(72) Inventors: **Jerry W Stevens**, Raleigh, NC (US); **Patricia G Drier**, Poughkeepsie, NY (US); **Constantinos Kassimis**, Research Triangle Park, NC (US); **Gary O. McAfee**, Research Triangle Park, NC (US); **Alexandra Winter**, Boeblingen (DE)

(73) Assignee: **International Business Machines Corporation**, Armonk, NY (US)

(*) Notice: Subject to any disclaimer, the term of this patent is extended or adjusted under 35 U.S.C. 154(b) by 264 days.

This patent is subject to a terminal disclaimer.

(21) Appl. No.: **13/948,157**

(22) Filed: **Jul. 22, 2013**

(65) **Prior Publication Data**

US 2015/0026314 A1 Jan. 22, 2015

(51) **Int. Cl.**
G06F 15/177 (2006.01)
G06F 15/167 (2006.01)
(Continued)

(52) **U.S. Cl.**
CPC **G06F 13/4027** (2013.01); **G06F 9/45558** (2013.01); **G06F 17/30595** (2013.01); **H04L 12/462** (2013.01); **H04L 12/4625** (2013.01); **H04L 41/0803** (2013.01);
(Continued)

(58) **Field of Classification Search**

CPC H04L 41/0206; H04L 41/0213; H04L 41/0803; H04L 41/0869; H04L 41/5035; H04L 41/5077; H04L 43/0882; H04L 43/0829; H04L 67/26; H04L 67/28; H04L 67/2842
USPC 709/212, 220, 225, 226, 216
See application file for complete search history.

(56) **References Cited**

U.S. PATENT DOCUMENTS

5,257,379 A 10/1993 Cwiakala
7,275,175 B2 9/2007 Cardona et al.
(Continued)

OTHER PUBLICATIONS

Buonadonna, "Queue-Pair IP: A Hybrid Architecture for System Area Networks"; Intel Research Berkeley; Mar. 2002; pp. 1-12.
(Continued)


Primary Examiner — Farzana Huq

(74) *Attorney, Agent, or Firm* — Stephen R. Tkacs; Stephen J. Walder, Jr.; Parashos T. Kalaitzis

(57) **ABSTRACT**

The disclosed network resource management system employs a hardware configuration management (HCM) information handling system (IHS) that may couple to a single administered IHS or to multiple administered IHSs via an administrative network. An HCM tool in the HCM IHS may generate, modify and store hardware configuration information, including physical network identifications (PNet IDs), in an HCM database and share the HCM database with the administered IHSs. The administered IHS may be a bridging IHS. A bridging tool may extract hardware configuration information, including PNet IDs, from the HCM database. The bridging tool may utilize the hardware configuration information, including PNet IDs, to enable the bridging IHS to bridge networks internal to the bridging IHS with networks external to the bridging IHS.

14 Claims, 34 Drawing Sheets



- (51) **Int. Cl.**
G06F 15/173 (2006.01)
G06F 13/40 (2006.01)
H04L 12/24 (2006.01)
H04L 12/931 (2013.01)
H04L 12/46 (2006.01)
G06F 17/30 (2006.01)
G06F 9/455 (2006.01)
- (52) **U.S. Cl.**
 CPC **H04L 49/65** (2013.01); **H04L 49/70**
 (2013.01); **G06F 2009/45579** (2013.01)

(56) **References Cited**

U.S. PATENT DOCUMENTS

| | | | | |
|--------------|-----|---------|--------------------|-------------------------|
| 7,940,706 | B2 | 5/2011 | Elko | |
| 8,036,229 | B2 | 10/2011 | Banerjee | |
| 2002/0059427 | A1 | 5/2002 | Tamaki et al. | |
| 2006/0282529 | A1 | 12/2006 | Nordin | |
| 2007/0002738 | A1 | 1/2007 | McGee | |
| 2011/0085563 | A1* | 4/2011 | Kotha | H04L 41/0816 370/401 |
| 2011/0093849 | A1* | 4/2011 | Chawla | H04L 41/0816 718/1 |
| 2011/0216669 | A1 | 9/2011 | Chawla et al. | |
| 2012/0317289 | A1 | 12/2012 | Fitzpatrick et al. | |
| 2013/0290541 | A1* | 10/2013 | Hatasaki | G06F 9/5077 709/226 |
| 2014/0010109 | A1 | 1/2014 | Himura et al. | |
| 2014/0213177 | A1* | 7/2014 | Terwilliger | H04W 24/04 455/41.1 |
| 2015/0012606 | A1 | 1/2015 | Gadipudi | |
| 2015/0026287 | A1 | 1/2015 | Stevens et al. | |
| 2015/0026313 | A1* | 1/2015 | Chawla | H04L 41/5035 709/220 |
| 2015/0026339 | A1 | 1/2015 | Stevens et al. | |
| 2015/0026677 | A1 | 1/2015 | Stevens et al. | |
| 2015/0339151 | A1 | 11/2015 | Stevens et al. | |
| 2015/0339161 | A1 | 11/2015 | Stevens et al. | |
| 2015/0339251 | A1 | 11/2015 | Stevens et al. | |
| 2015/0341354 | A1 | 11/2015 | Stevens et al. | |

OTHER PUBLICATIONS

Challa, "Comparative Study of Axial Flux Permanent Magnet Brushless DC Motor Operating With the Winding Connected in Single-Phase and Two-Phase System"; A Thesis Submitted to the Graduate Faculty of the Louisiana State University and Agricultural and Mechanical College in the Department of Electrical Engineering; Aug. 2006; pp. 1-8.

Ching, "Link Aggregation"; Thecus Blog; Jan. 14, 2013; pp. 1-5.

Dante, "Get Ready for a New Dimension in Computing."; System z Technical Education; IBM Advanced Technical Skills in Gaithersburg, Maryland; 2011; pp. 1-144.

Deek, The Impact of Channel Bonding on 802.11n Network Management; ACM CoNEXT 2011, Dec. 6-9 2011, Tokyo, Japan; pp. 1-12.

Feldman, "RoCE: An Ethernet-InfiniBand Love Story"; HPCwire, Apr. 22, 2010; pp. 1-11.

Filliater, "InfiniBand Technology and Usage Update"; Mellanox Technologies; SDC Storage Developer Conference, SNIA, Santa Clara; 2012; pp. 1-48.

Fischer, "Link Aggregation"; ADMIN Network & Security; © 2013 Linux New Media USA, LLC; pp. 1-4.

Fuller, "Sub-microsecond interconnects for processor connectivity—The opportunity"; EDN Networks, May 22, 2013; pp. 1-10.

Guijarro, "Experience and Lessons learnt from running High Availability Databases on Network Attached Storage"; International Conference on Computing in High Energy and Nuclear Physics (CHEP'07); Journal of Physics: Conference Series 119; 2008, IOP Publishing Ltd; pp. 1-10.

Hendel, Link Aggregation Trunking; Sun Microsystems IEEE 802—Tutorial Session Nov. 11, 1997; pp. 1-9.

Intel, "PCI-SIG SR-IOV Primer"; An Introduction to SR-IOV Technology; Jan. 2011; pp. 1-28.

Lowe, "What is SR-IOV?"; The weblog of an IT pro specializing in virtualization, storage, and servers; blog.scottlowe.org; Dec. 2, 2009; pp. 1-5.

Mellanox1, "RoCE vs. iWARP Competitive Analysis Brief"; Whitepaper; © Copyright 2010; Mellanox Technologies; www.mellanox.com; Nov. 2010; pp. 1-3.

Mellanox2, "InfiniBand Architecture Overview Back to Basic"; www.mellanox.com; © 2009 Mellanox Technologies; pp. 1-38.

Microsoft1, Overview of Single Root I/O Virtualization (SR-IOV); © 2013 Microsoft, Build date Jun. 19, 2013; p. 1.

Microsoft2, "SR-IOV/Architecture"; © 2013 Microsoft. Build date Jun. 19, 2013; pp. 1-3.

Microsoft3, "Overview of SR-IOV Data Paths"; © 2013 Microsoft; Build date Jun. 19, 2013; pp. 1-2.

QLogic, "NIC Partitioning and SR-IOV"; Technology Brief; 2012; pp. 1-4.

Recio, "RDMA enabled NIC (RNIC) Verbs Overview"; dated Apr. 29, 2003; available from http://www.rdmaconsortium.org/home/RNIC_Verbs_Overview2.pdf, pp. 1-28.

Rouse, "PCI Express (PCIe or PCI-E)"; SearchDataCenter.com; Mar. 28, 2008; p. 1.

Singh, "I/O Configuration Using z/OS HCD and HCM"; ibm.com/redbooks; Apr. 2010; pp. 1-462.

Stevens, "Network Virtualization, Management, and Security"; IBM zEnterprise System; © 2010 IBM Corporation; pp. 1-40.

Torres, "Everything You Need to Know About the PCI Express"; Hardware Secrets; Jul. 12, 2012; pp. 1-8.

Wiki, "RDMA over Converged Ethernet"; From Wikipedia; http://en.wikipedia.org/w/index.php?title=RDMA_13_over_Converged_Ethernet&oldid=564939508; last modified on Jul. 19, 2013; pp. 1-3.

Woodruff, "Introduction to the InfiniBand Core Software"; Proceedings of the Linux Symposium, vol. Two; Ottawa, Ontario Canada; Jul. 20-23, 2005; pp. 1-14.

ZCOPY, "Quick Concepts Part 1—Introduction to RDMA"; Education and Sample Code for RDMA Programming; Powered by WordPress.com; Posted on Oct. 8, 2010; pp. 1-6.

U.S. Appl. No. 13/948,151, Jan. 4, 2016.

U.S. Appl. No. 13/948,161, Dec. 4, 2015.

U.S. Appl. No. 13/948,163, Jan. 4, 2016.

U.S. Appl. No. 14/814,874, Dec. 3, 2015.

U.S. Appl. No. 14/814,949, Jan. 6, 2016.

U.S. Appl. No. 14/815,096, Dec. 3, 2015.

U.S. Appl. No. 14/815,191, Dec. 3, 2015.

"InfiniBand Architecture Overview Back to Basic", Mellanox Technologies, 2009 (month unknown), 38 pages.

"NIC Partitioning and SR-IOV", QLogic, http://www.qlogic.com/Resources/Documents/TechnologyBreifs/Adapters/NIC_Partitioning_and_SR-IOV_Channel.pdf, Technology Brief, Oct. 2012, 4 pages.

"Overview of Single Root I/O Virtualization (SR-IOV)", Microsoft, [https://msdn.microsoft.com/en-us/library/windows/hardware/hh440148\(v=vs.85\).aspx](https://msdn.microsoft.com/en-us/library/windows/hardware/hh440148(v=vs.85).aspx), Microsoft Developer Network, Build date: Jun. 19, 2013, 1 page.

"Overview of SR-IOV Data Paths", Microsoft, [https://msdn.microsoft.com/en-us/library/windows/hardware/hh440150\(v=vs.85\).aspx](https://msdn.microsoft.com/en-us/library/windows/hardware/hh440150(v=vs.85).aspx), Microsoft Developer Network, Build date: Jun. 19, 2013, 2 pages.

"PCI-SIG SR-IOV Primer", Intel, Intel LAN Access Division, An Introduction to SR-IOV Technology, Revision 2.5, Jan. 2011, 28 pages.

"Quick Concepts Part 1—Introduction to RDMA", WordPress.com, <https://zcopy.wordpress.com/2010/10/08/quick-concepts-oart-1-%E2%80000000%93-introduction-to-rdman/>, ZCopy, Education and Sample Code for RDMA Programming, Oct. 8, 2010, 6 pages.

"RDMA over Converged Ethernet", Wikipedia, http://en.wikipedia.org/w/index.php?title=RDMA_over_Converged_Ethernet&oldid=564939508, Jul. 19, 2013, 3 pages.

"RoCE vs. iWARP Competitive Analysis Brief", Mellanox Technologies, Whitepaper, Nov. 2010, 3 pages.

(56)

References Cited**OTHER PUBLICATIONS**

“SR-IOV Architecture”, Microsoft, [https://msdn.microsoft.com/en-us/library/windows/hardware/hh440238\(v=vs.85\).aspx](https://msdn.microsoft.com/en-us/library/windows/hardware/hh440238(v=vs.85).aspx), Microsoft Developer Network Build date: Jun. 19, 2013, 2 pages.

Buonadonna, Phil et al., “Queue-Pair IP: A Hybrid Architecture for System Area Networks”, Intel Corporation, Intel Research Berkeley, IRB-TR-02-002, Mar. 2002, 12 pages.

Challa, Sunil K., “Comparative Study of Axial Flux Permanent Magnet Brushless DC Motor Operating With the Winding Connected in Single-Phase and Two-Phase System”, Louisiana State University and Agricultural and Mechanical college, The Department of Electrical Engineering, Master of Science in Electrical Engineering Thesis, Aug. 2006, 81 pages.

Ching, “Link Aggregation”, Thecus, <http://blog.thecus.com/link-aggregation/>, Thecus Blog, Knowledge Base, Jan. 14, 2013, 5 pages.

Deek, Lara et al., “The Impact of Channel Bonding on 802.11n Network Management”, ACM, ACM CoNEXT 2011, Tokyo, Japan, Dec. 6-9, 2011, 12 pages.

Dente, Gwendolyn J., “Get Ready for a New Dimension in Computing”, IBM Corporation, IBM ATS zEnterprise System, System z Technical Education, IBM zEnterprise System Network Virtualization, Management, and Security, Month Unknown 2011, 144 pages.

Feldman, Michael, “RoCE: An Ethernet-InfiniBand Love Story”, HPCwire, http://www.hpcwire.com/hpcwire/2010-04-22/roceanethernet-infiniband_love_story.html, Apr. 22, 2010, 11 pages.

Filliater, Erin, “InfiniBand Technology and Usage Update”, Mellanox Technologies, Storage Developer Conference (SDC), SNIA, Santa Clara, CA, Sep. 17-20, 2012, 48 pages.

Fischer, Werner, “Link Aggregation”, Linux New Media USA, LLC, <http://www.admin-magazine.com/Articles/Increasing-Throughput->

with-Link-Aggregation, Admin Network & Security, Retrieved from the Internet May 28, 2013, 4 pages.

Fuller, Sam, “Submicrosecond interconnects for processor connectivity—The opportunity”, EDN Networks, May 22, 2013, 10 pages.

Guijarro, Manuel et al., “Experience and Lessons learnt from running High Availability Databases on Network Attached Storage”, IOP Publishing Ltd, International Conference on Computing in High Energy and Nuclear Physics (CHER07), Journal of Physics: Conference Series 119, No. 4, Jul. 2008, 10 pages.

Hendel, Ariel, “Link Aggregation Trunking”, Sun Microsystems, IEEE 802—Tutorial Session, Nov. 11, 1997, 9 pages.

Lowe, Scott, “What is SR-IOV?”, blog.scottlowe.org, <http://blog.scottlowe.org/2009/12/02/what-is-sr-iov/>, The weblog of an IT professional specializing in virtualization, storage, and servers, Dec. 2, 2009, 5 pages.

Recio, Renato, “RDMA enabled NIC (RNIC) Verbs Overview”, RDMA Consortium.org, http://www.rdmaconsortium.org/home/RNIC_Verbs_Overview2.pdf, Apr. 29, 2003, 28 pages.

Rouse, Margaret, “PCI Express (PCIe or PCI-E)”, TechTarget, SearchDataCenter.com, Mar. 28, 2008, 1 page.

Singh, Karan et al., “I/O Configuration Using z/Os HCD and HCM”, IBM Corporation, ibm.com/redbooks, Apr. 2010, Part I—231 pages.

Singh, Karan et al., “I/O Configuration Using z/Os HCD and HCM”, IBM Corporation, ibm.com/redbooks, Apr. 2010, Part II—231 pages.

Stevens, Jerry, “Network Virtualization, Management, and Security”, IBM Corporation, IBM zEnterprise System, Part 1: Overview, 2010 (month unknown), 40 pages.

Torres, Gabriel et al., “Everything You Need to Know About the PCI Express”, Hardware Secrets, Jul. 12, 2012, 8 pages.

Woodruff, Bob et al., “Introduction to the InfiniBand Core Software”, Ottawa Linux Symposium, Proceedings of the 2005 Linux Symposium, vol. 2, Ottawa, Canada, Jul. 20-23, 2005, 14 pages.

* cited by examiner




FIG. 2

200

| MSN | PID | LID | TYPE | LPAR ACCESS LIST | | | | | | | | PNET ID 1 | PNET ID 2 | |
|----------|------|------|------|------------------|----|----|----|----|----|----|--|--------------|--------------|-------|
| 0000880B | 0008 | 00F0 | 0087 | 01 | 02 | 03 | | | | | | NETA | NETA | 111 |
| 0000880B | 0020 | 0200 | 0008 | 01 | 02 | 03 | | | | | | NETA | NETA | 112 |
| 0000880B | 0009 | 00F4 | 0087 | 04 | 05 | | | | | | | NETB | NETB | 116 |
| 0000880B | 0021 | 0204 | 0008 | 04 | 05 | | | | | | | NETB | NETB | 117 |
| 0000880B | 020A | 00F7 | 0087 | 06 | 07 | | | | | | | NETC | NETC | 121 |
| 0000880B | 0222 | 0207 | 0008 | 06 | 07 | | | | | | | NETC | NETC | 122 |
| 0000880B | 0111 | 04C0 | 008D | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | | 129-1 |
| 0000880B | 0111 | 04C1 | 008D | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | | 129-2 |
| 0000880B | 0111 | 04C2 | 008D | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | | 129-3 |
| 0000880B | 0111 | 04C3 | 008D | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | | 129-4 |
| 0000880B | 0111 | 04C4 | 008D | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | | 129-5 |
| 0000880B | 0111 | 04C5 | 008D | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | | 129-6 |
| 0000880B | 0111 | 04C6 | 008D | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | | 129-7 |
| 8A0024FC | 0007 | 00B1 | 0087 | | | | | | | | | NETA | NETA | 114 |
| 8A0024FC | 0012 | 00C6 | 0008 | | | | | | | | | NETA | NETA | 115 |
| 578A7CE6 | 005A | 0200 | 0087 | | | | | | | | | NETB | NETB | 119 |
| 578A7CE6 | 0402 | 001C | 0008 | | | | | | | | | NETB | NETB | 120 |
| 578A7CE6 | 005B | 0201 | 0087 | | | | | | | | | NETC | NETC | 124 |
| 578A7CE6 | 0444 | 001D | 0008 | | | | | | | | | NETC | NETC | 125 |
| A453E85C | 0002 | 0105 | 0087 | | | | | | | | | NETC | NETC | 126 |
| A453E85C | 0005 | 00A2 | 0008 | | | | | | | | | NETC | NETC | 127 |




FIG. 4

400

| MSN | PID | LID | TYPE | LPAR ACCESS LIST | | | | | | | | PNET ID 1 | PNET ID 2 | |
|----------|------|------|------|------------------|----|----|----|----|----|----|--|--------------|--------------|-------|
| 000F880A | 0008 | 00F0 | 0087 | 01 | 02 | 03 | | | | | | NETA | NETA | 311 |
| 000F880A | 0009 | 00F1 | 0087 | 01 | 02 | 03 | | | | | | NETA | NETA | 312 |
| 000F880A | 020A | 0010 | 0008 | 01 | 02 | 03 | | | | | | NETA | NETA | 313 |
| 000F880A | 020B | 0011 | 0008 | 01 | 02 | 03 | | | | | | NETA | NETA | 314 |
| 000F880A | 0330 | 00F5 | 0087 | 04 | 05 | | | | | | | NETB | NETB | 318 |
| 000F880A | 0331 | 00F6 | 0087 | 04 | 05 | | | | | | | NETB | NETB | 319 |
| 000F880A | 020C | 0015 | 0008 | 04 | 05 | | | | | | | NETB | NETB | 320 |
| 000F880A | 020D | 0016 | 0008 | 04 | 05 | | | | | | | NETB | NETB | 321 |
| 000F880A | 0111 | 00F9 | 0087 | 06 | 07 | | | | | | | NETC | NETC | 327 |
| 000F880A | 0112 | 00FA | 0087 | 06 | 07 | | | | | | | NETC | NETC | 328 |
| 000F880A | 020E | 0019 | 0008 | 06 | 07 | | | | | | | NETC | NETC | 329 |
| 000F880A | 020F | 0020 | 0008 | 06 | 07 | | | | | | | NETC | NETC | 330 |
| 000F880A | 0222 | 06D0 | 008D | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | | 339-1 |
| 000F880A | 0222 | 06D1 | 008D | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | | 339-2 |
| 000F880A | 0222 | 06D2 | 008D | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | | 339-3 |
| 000F880A | 0222 | 06D3 | 008D | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | | 339-4 |
| 000F880A | 0222 | 06D4 | 008D | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | | 339-5 |
| 000F880A | 0222 | 06D5 | 008D | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | | 339-6 |
| 000F880A | 0222 | 06D6 | 008D | 01 | 02 | 03 | 04 | 05 | 06 | 07 | | | | 339-7 |
| A467E85D | 0005 | 00D1 | 0087 | | | | | | | | | NETA | NETA | 316 |
| A467E85D | 0016 | 0CB1 | 0008 | | | | | | | | | NETA | NETA | 317 |
| A467E85D | 0006 | 00D2 | 0087 | | | | | | | | | NETB | NETB | 323 |
| A467E85D | 0017 | 0CB2 | 0008 | | | | | | | | | NETB | NETB | 324 |
| 007A0052 | 00A1 | 00F0 | 0087 | | | | | | | | | NETB | NETB | 325 |
| 007A0052 | 00D1 | 00F1 | 0008 | | | | | | | | | NETB | NETB | 326 |
| 007A0052 | 00A2 | 00F2 | 0087 | | | | | | | | | NETC | NETC | 332 |
| 007A0052 | 00D2 | 00F3 | 0008 | | | | | | | | | NETC | NETC | 333 |
| C6200070 | 0016 | 00CA | 0087 | | | | | | | | | NETC | NETC | 334 |
| C6200070 | 0032 | 00CB | 0008 | | | | | | | | | NETC | NETC | 335 |
| C6200070 | 0022 | 00CC | 0087 | | | | | | | | | NETC | NETC | 336 |
| C6200070 | 000A | 00CD | 0008 | | | | | | | | | NETC | NETC | 337 |





FIG. 6

600




FIG. 8

800

| MSN | PID | LID | TYPE | LPAR ACCESS LIST | | | | | | | | PNET ID 1 | PNET ID 2 | |
|----------|------|------|------|------------------|----|----|--|--|--|--|--|--------------|--------------|-----|
| 00D5380C | 0008 | 00F0 | 0087 | 01 | 02 | 03 | | | | | | NETA | NETA | 711 |
| 00D5380C | 0009 | 02F0 | 0008 | 01 | 02 | 03 | | | | | | NETA | NETA | 712 |
| 00D5380C | 020A | 00F4 | 0087 | 04 | 05 | | | | | | | NETB | NETB | 716 |
| 00D5380C | 020B | 02F4 | 0008 | 04 | 05 | | | | | | | NETB | NETB | 717 |
| 00D5380C | 0330 | 00F7 | 0087 | 06 | 07 | | | | | | | NETC | NETC | 721 |
| 00D5380C | 0331 | 02F7 | 0008 | 06 | 07 | | | | | | | NETC | NETC | 722 |
| 0007880A | 020C | 0022 | 0087 | | | | | | | | | NETA | NETA | 714 |
| 0007880A | 020D | 0023 | 0008 | | | | | | | | | NETA | NETA | 715 |
| 003F230A | 0111 | 0DA1 | 0087 | | | | | | | | | NETB | NETB | 719 |
| 003F230A | 0112 | 0DA2 | 0008 | | | | | | | | | NETB | NETB | 720 |
| 003F230A | 020E | 0024 | 0087 | | | | | | | | | NETC | NETC | 724 |
| 003F230A | 020F | 0025 | 0008 | | | | | | | | | NETC | NETC | 725 |
| 668A2B01 | 0117 | 06D0 | 0087 | | | | | | | | | NETC | NETC | 726 |

FIG. 9




FIG. 10

1000

| MSN | PID | LID | TYPE | LPAR ACCESS LIST | | | | | | | | PNET ID 1 | PNET ID 2 | |
|----------|------|------|------|------------------|----|----|----|----|----|----|----|--------------|--------------|-----|
| 000F3801 | 0011 | 00F0 | 0087 | 01 | 02 | 03 | 04 | 08 | 09 | 0A | 0B | NETA | NETA | 909 |
| 000F3801 | 0020 | 05C0 | 0008 | 01 | 02 | 03 | 04 | 08 | 09 | 0A | 0B | NETA | NETA | 910 |
| 000F3801 | 0012 | 00F9 | 0087 | 04 | 05 | 06 | 07 | | | | | NETA | NETA | 911 |
| 000F3801 | 0021 | 05C9 | 0008 | 04 | 05 | 06 | 07 | | | | | NETA | NETA | 912 |
| 000F3801 | 0013 | 00FE | 0087 | 03 | | | | | | | | NETA | NETA | 913 |
| 000F3801 | 0022 | 05CE | 0008 | 03 | | | | | | | | NETA | NETA | 914 |
| 000F3801 | 0014 | 0100 | 0087 | 02 | 04 | 06 | 08 | 0A | | | | NETA | NETA | 915 |
| 000F3801 | 0023 | 0600 | 0008 | 02 | 04 | 06 | 08 | 0A | | | | NETA | NETA | 916 |
| 000F3801 | 0015 | 0106 | 0087 | 01 | 02 | 03 | 04 | 05 | 06 | 07 | 08 | NETA | NETA | 917 |
| 000F3801 | 0016 | 010F | 0087 | 01 | 02 | 03 | 04 | 07 | 09 | 0A | 0B | NETA | NETA | 918 |
| 000F3801 | 0017 | 0118 | 0087 | 01 | 03 | 05 | 07 | 08 | 09 | 0A | 0B | NETA | NETA | 919 |
| 000F3801 | 0018 | 0120 | 0087 | 01 | 02 | 03 | 04 | 05 | 06 | 07 | 08 | NETB | NETB | 925 |
| 000F3801 | 0024 | 0606 | 0008 | 01 | 02 | 03 | 04 | 05 | 06 | 07 | 08 | NETB | NETB | 926 |
| 000F3801 | 0019 | 0129 | 0087 | 09 | 0A | 0B | | | | | | NETB | NETB | 927 |
| 000F3801 | 0025 | 060F | 0008 | 09 | 0A | 0B | | | | | | NETB | NETB | 928 |
| 000F3801 | 001A | 012D | 0087 | 01 | 03 | 05 | 07 | | | | | NETB | NETB | 929 |
| 000F3801 | 0026 | 0613 | 0008 | 01 | 03 | 05 | 07 | | | | | NETB | NETB | 930 |
| 000F3801 | 0027 | 0618 | 0008 | 01 | 02 | 03 | 04 | 05 | 06 | 07 | 08 | NETB | NETB | 931 |
| 000F3801 | 0028 | 0621 | 0008 | 01 | 02 | 03 | 04 | 07 | 09 | 0A | 0B | NETB | NETB | 932 |
| 000F3801 | 0029 | 062A | 0008 | 01 | 02 | 03 | 04 | 05 | 06 | 07 | 08 | NETB | NETB | 933 |
| 000F3801 | 002A | 0633 | 0008 | 01 | 02 | 03 | 04 | 07 | 09 | 0A | 0B | NETB | NETB | 934 |
| 03006FF7 | 0101 | 0F01 | 0087 | | | | | | | | | NETA | NETA | 921 |
| 03006FF7 | 0201 | 0F02 | 0008 | | | | | | | | | NETA | NETA | 922 |
| 03006FF7 | 0102 | 0F03 | 0087 | | | | | | | | | NETA | NETA | 923 |
| 03006FF7 | 0202 | 0F04 | 0008 | | | | | | | | | NETA | NETA | 924 |
| D832900A | 0055 | DD06 | 0087 | | | | | | | | | NETB | NETB | 936 |
| D832900A | 0057 | DD07 | 0008 | | | | | | | | | NETB | NETB | 937 |
| D832900A | 0056 | DD08 | 0087 | | | | | | | | | NETB | NETB | 938 |
| D832900A | 0058 | DD09 | 0008 | | | | | | | | | NETB | NETB | 939 |





FIG. 12

1200




FIG. 14

1400

| MSN | PID | LID | TYPE | LPAR ACCESS LIST | | | | | | | | PNET ID 1 | PNET ID 2 | |
|----------|------|------|------|------------------|----|----|--|--|--|--|--|--------------|--------------|--------|
| 0A0A0B11 | 0006 | 00F1 | 0087 | 01 | 02 | 03 | | | | | | NETA | NETA | 1311 |
| 0A0A0B11 | 0007 | 00F5 | 0087 | 04 | 05 | | | | | | | NETB | NETB | 1314 |
| 0A0A0B11 | 0008 | 00F8 | 0087 | 06 | 07 | | | | | | | NETC | NETC | 1317 |
| 0A0A0B11 | 0112 | 04C1 | 008D | 01 | 02 | 03 | | | | | | NETA | | 1321-1 |
| 0A0A0B11 | 0112 | 04C2 | 008D | 01 | 02 | 03 | | | | | | NETA | | 1321-2 |
| 0A0A0B11 | 0112 | 04C3 | 008D | 01 | 02 | 03 | | | | | | NETA | | 1321-3 |
| 0A0A0B11 | 0113 | 04C5 | 008D | 04 | 05 | | | | | | | NETB | | 1321-4 |
| 0A0A0B11 | 0113 | 04C6 | 008D | 04 | 05 | | | | | | | NETB | | 1321-5 |
| 0A0A0B11 | 0114 | 04C8 | 008D | 06 | 07 | | | | | | | NETC | | 1321-6 |
| 0A0A0B11 | 0114 | 04C9 | 008D | 06 | 07 | | | | | | | NETC | | 1321-7 |
| 0000F12A | 0022 | 0DA1 | 0087 | | | | | | | | | NETA | NETA | 1313 |
| DDD32AA | 0054 | 00C1 | 0087 | | | | | | | | | NETB | NETB | 1316 |
| 000000B2 | 0001 | 0DD4 | 0087 | | | | | | | | | NETC | NETC | 1319 |




FIG. 16

1600

| MSN | PID | LID | TYPE | LPAR ACCESS LIST | | | | | | | | PNET ID 1 | PNET ID 2 | |
|----------|------|------|------|------------------|----|----|----|--|--|--|--|--------------|--------------|--------|
| 03F00A21 | 0006 | 00F1 | 0087 | 01 | 02 | 03 | | | | | | NETA | NETA | 1509 |
| 03F00A21 | 0007 | 00F5 | 0087 | 04 | 05 | 06 | 07 | | | | | NETB | NETB | 1512 |
| 03F00A21 | 0111 | 04C0 | 008D | 01 | 02 | 03 | | | | | | NETA | | 1516-1 |
| 03F00A21 | 0111 | 04C1 | 008D | 01 | 02 | 03 | | | | | | NETA | | 1516-2 |
| 03F00A21 | 0111 | 04C2 | 008D | 01 | 02 | 03 | | | | | | NETA | | 1516-3 |
| 03F00A21 | 0112 | 04C4 | 008D | 04 | 05 | 06 | 07 | | | | | NETB | | 1516-4 |
| 03F00A21 | 0112 | 04C5 | 008D | 04 | 05 | 06 | 07 | | | | | NETB | | 1516-5 |
| 03F00A21 | 0112 | 04C6 | 008D | 04 | 05 | 06 | 07 | | | | | NETB | | 1516-6 |
| 03F00A21 | 0112 | 04C7 | 008D | 04 | 05 | 06 | 07 | | | | | NETB | | 1516-7 |
| 31400ADA | 0031 | 00F3 | 0087 | | | | | | | | | NETA | NETA | 1511 |
| 2338282D | 0022 | 0DA1 | 0087 | 01 | 02 | | | | | | | NETB | NETB | 1514 |
| 2338282D | 0200 | 06D1 | 008D | 01 | 02 | | | | | | | NETB | | 1524-1 |
| 2338282D | 0200 | 06D2 | 008D | 01 | 02 | | | | | | | NETB | | 1524-2 |




FIG. 18


1800

FIG. 20

2000

| MSN | PID | LID | TYPE | LPAR ACCESS LIST | | | | | | | | PNET ID 1 | PNET ID 2 | |
|----------|------|------|------|------------------|----|----|--|--|--|--|--|--------------|--------------|------|
| 0000FFA1 | 0006 | 00F1 | 0087 | 01 | 02 | 03 | | | | | | NETA | NETA | 1911 |
| 0000FFA1 | 0007 | 00F5 | 0087 | 01 | 02 | 03 | | | | | | NETA | NETA | 1912 |
| 0000FFA1 | 0111 | 04C0 | 0008 | 01 | 02 | 03 | | | | | | NETA | NETA | 1913 |
| 0000FFA1 | 0112 | 04C4 | 0008 | 01 | 02 | 03 | | | | | | NETA | NETA | 1914 |
| 0000FFA1 | 0008 | 00F9 | 0087 | 04 | 05 | | | | | | | NETB | NETB | 1920 |
| 0000FFA1 | 0009 | 00FC | 0087 | 04 | 05 | | | | | | | NETB | NETB | 1921 |
| 0000FFA1 | 0113 | 04C8 | 0008 | 04 | 05 | | | | | | | NETB | NETB | 1922 |
| 0000FFA1 | 0114 | 04CB | 0008 | 04 | 05 | | | | | | | NETB | NETB | 1923 |
| 0000FFA1 | 000A | 00FF | 0087 | 06 | 07 | | | | | | | NETC | NETC | 1929 |
| 0000FFA1 | 000B | 0102 | 0087 | 06 | 07 | | | | | | | NETC | NETC | 1930 |
| 0000FFA1 | 0115 | 04CE | 0008 | 06 | 07 | | | | | | | NETC | NETC | 1931 |
| 0000FFA1 | 0116 | 04D1 | 0008 | 06 | 07 | | | | | | | NETC | NETC | 1932 |
| 00DDA254 | 0001 | 00A3 | 0087 | | | | | | | | | NETA | NETA | 1916 |
| 00DDA254 | 0003 | 00B1 | 0008 | | | | | | | | | NETA | NETA | 1917 |
| 00DDA254 | 0002 | 00A4 | 0087 | | | | | | | | | NETA | NETA | 1918 |
| 00DDA254 | 0004 | 00B2 | 0008 | | | | | | | | | NETA | NETA | 1919 |
| FAF33922 | 0023 | 00F6 | 0087 | | | | | | | | | NETB | NETB | 1925 |
| FAF33922 | 0032 | 00FF | 0008 | | | | | | | | | NETB | NETB | 1926 |
| FAF33922 | 0024 | 00F7 | 0087 | | | | | | | | | NETB | NETB | 1927 |
| FAF33922 | 0033 | 0100 | 0008 | | | | | | | | | NETB | NETB | 1928 |
| 363B77A2 | 0011 | 00C2 | 0087 | | | | | | | | | NETC | NETC | 1934 |
| 363B77A2 | 0002 | 0D01 | 0008 | | | | | | | | | NETC | NETC | 1935 |
| 363B77A2 | 0012 | 00C3 | 0087 | | | | | | | | | NETC | NETC | 1936 |
| 363B77A2 | 0003 | 0D02 | 0008 | | | | | | | | | NETC | NETC | 1937 |




FIG. 22

2200

| MSN | PID | LID | TYPE | LPAR ACCESS LIST | | | | | | | | PNET ID 1 | PNET ID 2 | |
|----------|------|------|------|------------------|----|----|--|--|--|--|--|-----------|-----------|------|
| 0DC0FFB2 | 0001 | 00F1 | 0087 | 01 | 02 | 03 | | | | | | NETA | NETA | 2109 |
| 0DC0FFB2 | 0002 | 00F5 | 0087 | 01 | 02 | 03 | | | | | | NETA | NETA | 2110 |
| 0DC0FFB2 | 0111 | 0FF1 | 0008 | 01 | 02 | 03 | | | | | | NETA | NETA | 2111 |
| 0DC0FFB2 | 0112 | 0FF5 | 0008 | 01 | 02 | 03 | | | | | | NETA | NETA | 2112 |
| 0DC0FFB2 | 0003 | 00F9 | 0087 | 01 | 02 | 03 | | | | | | NETA | NETA | 2113 |
| 0DC0FFB2 | 0113 | 0FF9 | 0008 | 01 | 02 | 03 | | | | | | NETA | NETA | 2114 |
| 0DC0FFB2 | 0004 | 00FD | 0087 | 04 | 05 | | | | | | | NETB | NETB | 2120 |
| 0DC0FFB2 | 0114 | 0FFD | 0008 | 04 | 05 | | | | | | | NETB | NETB | 2121 |
| 0DC0FFB2 | 0005 | 0100 | 0087 | 04 | 05 | | | | | | | NETB | NETB | 2122 |
| 0DC0FFB2 | 0006 | 0103 | 0087 | 04 | 05 | | | | | | | NETB | NETB | 2123 |
| 0DC0FFB2 | 0115 | 1000 | 0008 | 04 | 05 | | | | | | | NETB | NETB | 2124 |
| 0DC0FFB2 | 0116 | 1003 | 0008 | 04 | 05 | | | | | | | NETB | NETB | 2125 |
| 0000D100 | 0033 | 0D01 | 0087 | | | | | | | | | NETA | NETA | 2116 |
| 0000D100 | 0025 | 0D03 | 0008 | | | | | | | | | NETA | NETA | 2117 |
| 0000D100 | 0034 | 0D02 | 0087 | | | | | | | | | NETA | NETA | 2118 |
| 0000D100 | 0026 | 0D04 | 0008 | | | | | | | | | NETA | NETA | 2119 |
| FFFFA200 | 0011 | 000A | 0087 | 01 | 02 | | | | | | | NETB | NETB | 2127 |
| FFFFA200 | 0012 | 000B | 0087 | 01 | 02 | | | | | | | NETB | NETB | 2128 |
| FFFFA200 | 0021 | 0F01 | 0008 | 01 | 02 | | | | | | | NETB | NETB | 2129 |
| FFFFA200 | 0022 | 0F02 | 0008 | 01 | 02 | | | | | | | NETB | NETB | 2130 |






FIG. 24

2400






FIG. 25B

FIG. 26


2600

| MSN | PID | LID | TYPE | LPAR ACCESS LIST | | | | | | | | PNET ID 1 | PNET ID 2 | |
|----------|------|------|------|------------------|----|----|--|--|--|--|--|-----------|-----------|------|
| 0CCC0AB2 | 0001 | 00F1 | 0087 | 01 | 02 | 03 | | | | | | NETA | NETA | 2512 |
| 0CCC0AB2 | 0111 | 00A1 | 0008 | 01 | 02 | 03 | | | | | | NETA | NETA | 2513 |
| 0CCC0AB2 | 0002 | 00F5 | 0087 | 04 | 05 | | | | | | | NETB | NETB | 2517 |
| 0CCC0AB2 | 0112 | 00A5 | 0008 | 04 | 05 | | | | | | | NETB | NETB | 2518 |
| 0CCC0AB2 | 0003 | 00F8 | 0087 | 06 | 07 | | | | | | | NETC | NETC | 2522 |
| 0CCC0AB2 | 0113 | 00A8 | 0008 | 06 | 07 | | | | | | | NETC | NETC | 2523 |
| DFA22601 | 0001 | 00F4 | 0087 | | | | | | | | | NETA | NETA | 2515 |
| DFA22601 | 0002 | 00A4 | 0008 | | | | | | | | | NETA | NETA | 2516 |
| 33300FB8 | 0001 | 00F5 | 0087 | | | | | | | | | NETB | NETB | 2520 |
| 33300FB8 | 0011 | 00F6 | 0008 | | | | | | | | | NETB | NETB | 2521 |
| 33300FB8 | 0002 | 00A5 | 0087 | | | | | | | | | NETC | NETC | 2525 |
| 33300FB8 | 0012 | 00A6 | 0008 | | | | | | | | | NETC | NETC | 2526 |
| 0000FC32 | 0031 | 0D01 | 0087 | | | | | | | | | NETC | NETC | 2527 |
| 0000FC32 | 0033 | 0D03 | 0008 | | | | | | | | | NETC | NETC | 2528 |

FIG. 27

2700

| PNET ID | MSN | LPAR ACCESS LIST | | | | | | | |
|---------|----------|------------------|----|--|--|--|--|--|--|
| NETB | 0CCC0AB2 | 04 | 05 | | | | | | |
| NETB | 33300FB8 | | | | | | | | |
| NETC | 0CCC0AB2 | 07 | | | | | | | |
| NETC | 33300FB8 | | | | | | | | |
| NETC | 0000FC32 | | | | | | | | |






FIG. 28B

FIG. 29


2900

| MSN | PID | LID | TYPE | LPAR ACCESS LIST | | | | | | | | PNET ID 1 | PNET ID 2 | |
|----------|------|------|------|------------------|----|----|--|--|--|--|--|-----------|-----------|------|
| 000AFA11 | 0001 | 00F1 | 0087 | 01 | 02 | 03 | | | | | | NETA | NETA | 2812 |
| 000AFA11 | 0002 | 00F5 | 0087 | 01 | 02 | 03 | | | | | | NETA | NETA | 2813 |
| 000AFA11 | 0011 | 00A1 | 0008 | 01 | 02 | 03 | | | | | | NETA | NETA | 2814 |
| 000AFA11 | 0012 | 00A5 | 0008 | 01 | 02 | 03 | | | | | | NETA | NETA | 2815 |
| 000AFA11 | 0003 | 00F9 | 0087 | 04 | 05 | | | | | | | NETB | NETB | 2819 |
| 000AFA11 | 0004 | 00FC | 0087 | 04 | 05 | | | | | | | NETB | NETB | 2820 |
| 000AFA11 | 0013 | 00A9 | 0008 | 04 | 05 | | | | | | | NETB | NETB | 2821 |
| 000AFA11 | 0014 | 00AC | 0008 | 04 | 05 | | | | | | | NETB | NETB | 2822 |
| 000AFA11 | 0005 | 00FF | 0087 | 06 | 07 | | | | | | | NETC | NETC | 2830 |
| 000AFA11 | 0006 | 0102 | 0087 | 06 | 07 | | | | | | | NETC | NETC | 2831 |
| 000AFA11 | 0015 | 00AF | 0008 | 06 | 07 | | | | | | | NETC | NETC | 2832 |
| 000AFA11 | 0016 | 00B2 | 0008 | 06 | 07 | | | | | | | NETC | NETC | 2833 |
| 0000FC32 | 0001 | 0D01 | 0087 | | | | | | | | | NETA | NETA | 2817 |
| 0000FC32 | 0021 | 0D03 | 0008 | | | | | | | | | NETA | NETA | 2818 |
| 0000FC32 | 0002 | 0D02 | 0087 | | | | | | | | | NETB | NETB | 2824 |
| 0000FC32 | 0022 | 0D04 | 0008 | | | | | | | | | NETB | NETB | 2825 |
| DDDD00AB | 0001 | 0C01 | 0087 | | | | | | | | | NETB | NETB | 2826 |
| DDDD00AB | 0011 | 0C03 | 0008 | | | | | | | | | NETB | NETB | 2827 |
| DDDD00AB | 0002 | 0C02 | 0087 | | | | | | | | | NETB | NETB | 2828 |
| DDDD00AB | 0022 | 0C04 | 0008 | | | | | | | | | NETB | NETB | 2829 |
| ACA000F1 | 0001 | 00B1 | 0087 | 01 | 02 | | | | | | | NETC | NETC | 2835 |
| ACA000F1 | 0002 | 00B4 | 0087 | 01 | 02 | | | | | | | NETC | NETC | 2836 |
| ACA000F1 | 0021 | 00C1 | 0008 | 01 | 02 | | | | | | | NETC | NETC | 2837 |
| ACA000F1 | 0022 | 00C4 | 0008 | 01 | 02 | | | | | | | NETC | NETC | 2838 |

FIG. 30

3000

| PNET ID | MSN | LPAR ACCESS LIST | | | | | | | |
|---------|----------|------------------|----|--|--|--|--|--|--|
| NETB | 000AFA11 | 04 | 05 | | | | | | |
| NETB | 0000FC32 | | | | | | | | |
| NETB | DDDD00AB | | | | | | | | |
| NETC | 000AFA11 | 07 | | | | | | | |
| NETC | ACA000F1 | 02 | | | | | | | |






FIG. 33



3300

FIG. 34

3400

1

NETWORK RESOURCE MANAGEMENT SYSTEM UTILIZING PHYSICAL NETWORK IDENTIFICATION FOR BRIDGING OPERATIONS

BACKGROUND

The disclosures herein relate generally to information handling systems (IHSs), and more specifically, to IHSs that communicate with other particular IHSs. Multiple IHSs may be connected together via a communication network. Multiple IHSs may also be connected together via multiple communication networks. A hardware configuration management system on a first IHS may share information about the hardware configuration of a second IHS via a communication network.

BRIEF SUMMARY

In one embodiment, a method for bridging operations in an information handling system (IHS) is provided. The method includes receiving, by a hypervisor of a first IHS, an HCM database that includes configuration information including physical network identifier (PNet ID) entries and respective associated physical adapter type entries and respective associated logical partition (LPAR) access information entries. The method also includes transmitting, by the hypervisor of the first IHS, the HCM database to a bridging tool. The method further includes extracting, by the bridging tool, configuration information from the HCM database, the configuration information including PNet ID entries and respective associated physical adapter ID entries and respective associated logical partition (LPAR) access information entries, thus providing extracted physical bridging configuration information. The method still further includes extracting, by the bridging tool, configuration information from the HCM database, the configuration information including PNet ID entries and respective associated virtual adapter ID entries and respective associated logical partition (LPAR) access information entries, thus providing extracted virtual bridging configuration information. The method also includes bridging via a virtual switch, by the bridging tool, a physical adapter in the first IHS and a virtual adapter in the first IHS that exhibit a same PNet ID.

BRIEF DESCRIPTION OF THE DRAWINGS

The appended drawings illustrate only exemplary embodiments of the invention and therefore do not limit its scope because the inventive concepts lend themselves to other equally effective embodiments.

FIG. 1 is a block diagram showing one embodiment of the disclosed hardware configuration management (HCM) system utilizing physical network identifiers (PNet IDs).

FIG. 2 depicts one embodiment of an HCM database that may be used in the disclosed HCM system.

FIG. 3 is a block diagram showing another embodiment of the disclosed HCM system utilizing PNet IDs.

FIG. 4 depicts one embodiment of the HCM database that may be used in the disclosed HCM system.

FIG. 5 is a block diagram of an HCM information handling system (IHS) that may be used in the disclosed HCM system.

FIG. 6 is a flowchart that shows a representative process flow of an HCM tool that may be used in the disclosed HCM system.

2

FIG. 7 is a block diagram showing one embodiment of the disclosed remote direct memory access (RDMA) enabled network adapter controller (RNIC) converging system utilizing PNet IDs.

FIG. 8 depicts one embodiment of an HCM database that may be used in the disclosed RNIC converging system.

FIG. 9 is a block diagram showing another embodiment of the disclosed RNIC converging system utilizing PNet IDs.

FIG. 10 depicts one embodiment of the HCM database that may be used in the disclosed RNIC converging system.

FIG. 11 is a block diagram of an RNIC converging IHS that may be used in the disclosed RNIC converging system.

FIG. 12 is a flowchart that shows a representative process flow of an RNIC converging tool that may be used in the disclosed RNIC converging system.

FIG. 13 is a block diagram showing one embodiment of the disclosed bridging system utilizing PNet IDs.

FIG. 14 depicts one embodiment of a HCM database that may be used in the disclosed bridging system.

FIG. 15 is a block diagram showing another embodiment of the disclosed bridging system utilizing PNet IDs.

FIG. 16 depicts one embodiment of the HCM database that may be used in the disclosed bridging system.

FIG. 17 is a block diagram of a bridging IHS that may be used in the disclosed bridging system.

FIG. 18 is a flowchart that shows a representative process flow of a bridging tool that may be used in the disclosed bridging system.

FIG. 19 is a block diagram showing one embodiment of the disclosed load balancing system utilizing PNet IDs.

FIG. 20 depicts one embodiment of a HCM database that may be used in the disclosed load balancing system.

FIG. 21 is a block diagram showing another embodiment of the disclosed load balancing system utilizing PNet IDs.

FIG. 22 depicts one embodiment of the HCM database that may be used in the disclosed load balancing system.

FIG. 23 is a block diagram of a load balancing IHS that may be used in the disclosed load balancing system.

FIG. 24 is a flowchart that shows a representative process flow of a load balancing tool that may be used in the disclosed load balancing system.

FIGS. 25A and 25B are block diagrams showing one embodiment of the disclosed privileged network access (PNA) system utilizing PNet IDs.

FIG. 26 depicts one embodiment of a HCM database that may be used in the disclosed privileged network access (PNA) system.

FIG. 27 depicts one embodiment of a privileged network access management (PNAM) database that may be used in the disclosed privileged network access system.

FIGS. 28A and 28B are block diagrams showing another embodiment of the disclosed privileged network access (PNA) system utilizing PNet IDs.

FIG. 29 depicts one embodiment of the HCM database that may be used in the disclosed privileged network access (PNA) system.

FIG. 30 depicts one embodiment of the PNA database that may be used in the disclosed privileged network access (PNA) system.

FIG. 31 is a block diagram of a privileged network access IHS that may be used in the disclosed privileged network access (PNA) system.

FIG. 32 is a block diagram of a privileged network access management (PNAM) IHS that may be used in the disclosed privileged network access system.

FIG. 33 is a flowchart that shows a representative process flow of a privileged network access tool (PNA) that may be used in the disclosed privileged network access system.

FIG. 34 is a flowchart that shows a representative process flow of a privileged network access management (PNAM) tool that may be used in the disclosed privileged network access system.

DETAILED DESCRIPTION

The disclosed network resource management system employs a hardware configuration management (HCM) information handling system (IHS) that may couple to a single administered IHS or to multiple administered IHSs via an administrative network. An HCM tool in the HCM IHS may generate, modify and store hardware configuration management information in an HCM database in the HCM IHS. The HCM database stores hardware configuration information that may include, but is not limited to, machine serial numbers (MSNs), physical identifications (PIDs), logical identifications (LIDs), types, logical partition (LPAR) access lists and physical network identifications (PNet IDs). A PNet ID is an identifier that informs an IHS with respect to a particular network to which an adapter of the IHS connects, as explained in more detail below.

In one embodiment, the HCM tool may transmit the HCM database to a hypervisor agent of an administered IHS via the administrative network. In another embodiment, the HCM tool may transmit the HCM database to a hypervisor agent of an administered IHS via a serial connection. The hypervisor agent of the administered IHS may receive the HCM database and allow the hypervisor of the administered IHS to access the HCM database.

In one embodiment, the administered IHS may be a remote direct memory access (RDMA) enabled network interface controller (RNIC) converging IHS. RDMA is remote direct memory access, a technology that enables an IHS to exchange information with another IHS without involving the processor, cache or operating system. The hypervisor of the RNIC converging IHS may transmit the HCM database to an RNIC converging tool in the RNIC converging IHS. The RNIC converging tool may extract hardware configuration information from the HCM database. The RNIC converging tool may utilize the hardware configuration information to enable the RNIC converging IHS to communicate over a network with RDMA protocols, as discussed in more detail below.

In another embodiment, the administered IHS may be a bridging IHS. The hypervisor of the bridging IHS may transmit the HCM database to a bridging tool in the bridging IHS. The bridging tool may extract hardware configuration information from the HCM database. The bridging tool may utilize the hardware configuration information to enable the bridging IHS to bridge networks internal to the bridging IHS with networks external to the bridging IHS, as discussed in more detail below.

In another embodiment, the administered IHS may be a load balancing IHS. The hypervisor of the load balancing IHS may transmit the HCM database to a load balancing tool in the load balancing IHS. The load balancing tool may extract hardware configuration information from the HCM database. The load balancing tool may utilize the hardware configuration information to enable the load balancing IHS to balance adapter loads in the load balancing IHS. The load balancing tool may also utilize the hardware configuration information to enable the load balancing IHS to failover from a failing adapter to other adapters in the load balancing IHS, as discussed in more detail below.

In another embodiment, the administered IHS may be a privileged network access (PNA) IHS. The hypervisor agent of the PNA IHS may receive a privileged network access management (PNAM) database from a PNA tool in a PNA IHS via the administrative network. The hypervisor agent of the PNA IHS may allow the hypervisor of the PNA IHS to access the PNA database. The hypervisor of the PNA IHS may transmit the HCM database and the PNA database to a PNA tool in the PNA IHS. The PNA tool may extract hardware configuration information from the HCM database and privileged network access information from the PNA database. The PNA tool may utilize the hardware configuration information and privileged network access information to enable the PNA IHS to limit access to privileged networks, as discussed in more detail below.

1. HCM System

FIG. 1 is a block diagram showing one embodiment of the disclosed hardware configuration management (HCM) system 100 utilizing physical network identifiers (PNet IDs). HCM system 100 may utilize network adapter 101, administrative network 102 and network adapter 103 to couple HCM IHS 500 to administered IHS 104. HCM system 100 may utilize network adapter 101, administrative network 102 and network adapter 105 to couple HCM IHS 500 to administered IHS 106. HCM system 100 may utilize network adapter 101, administrative network 102 and network adapter 107 to couple HCM IHS 500 to administered IHS 108. HCM system 100 may utilize network adapter 101, administrative network 102 and network adapter 109 to couple HCM IHS 500 to administered IHS 110. Administered IHSs 104, 106, 108 and 110 couple via administrative network 102 to HCM IHS 500 to enable HCM IHS 500 to administer HCM database 200 with HCM tool 600 to the administered IHSs.

HCM system 100 may utilize network adapter 111 and/or network adapter 112 via NETWORK A 113 via network adapter 114 and/or network adapter 115 to couple administered IHS 104 to administered IHS 106. HCM system 100 may utilize network adapter 116 and/or network adapter 117 via NETWORK B 118 via network adapter 119 and/or network adapter 120 to couple administered IHS 104 to administered IHS 108. HCM system 100 may utilize network adapter 121 and/or network adapter 122 via NETWORK C 123 via network adapter 124 and/or network adapter 125 to couple administered IHS 104 to administered IHS 108. HCM system 100 may utilize network adapter 121 and/or network adapter 122 via NETWORK C 123 via network adapter 126 and/or network adapter 127 to couple administered IHS 104 to administered IHS 110.

In one embodiment, network adapter 101, 103, 105, 107 and 109 may be Ethernet (ETH) adapters. Network adapters 111, 114, 116, 119, 121, 124 and 126 may be open system adapters (OSAs). Network adapters 112, 115, 117, 120, 122, 125 and network adapter 127 may be remote direct memory access (RDMA) enabled network adapter controllers (RNICs). In one embodiment, administrative network 102, NETWORK A 113, NETWORK B 118 and NETWORK C 123 may provide local area network (LAN) communications and/or wide area network (WAN) communications and/or virtual LAN communications and/or intranet communications and/or Internet communications to structures that couple thereto.

Administered IHS 104 may include a hypervisor (not shown) that may create logical partition (LPAR) 128-1, LPAR 128-2, LPAR 128-3, LPAR 128-4, LPAR 128-5, LPAR 128-6 and LPAR 128-7 in administered IHS 104. LPAR 128-1, LPAR 128-2, LPAR 128-3, LPAR 128-4, LPAR 128-5, LPAR 128-6 and LPAR 128-7 may respectively include vir-

tual internal network adapter **129-1**, virtual internal network adapter **129-2**, virtual internal network adapter **129-3**, virtual internal network adapter **129-4**, virtual internal network adapter **129-5**, virtual internal network adapter **129-6** and virtual internal network adapter **129-7**. Virtual internal network adapter **129-1**, **129-2**, **129-3**, **129-4**, **129-5**, **129-6** and **129-7** may be internal queued direct (IQD) communication adapters and couple to one another via administered IHS **104** IQD network **130**. Administered IHS **104** IQD network **130** may be a channel, i.e., a bus.

LPAR **128-1**, LPAR **128-2** and LPAR **128-3** may include virtual network adapter **131-1**, virtual network adapter **131-2** and virtual network adapter **131-3**, respectively. Virtual network adapter **131-1**, virtual network adapter **131-2** and virtual network adapter **131-3** may couple to network adapter **111** via a channel. LPAR **128-4** and LPAR **128-5** may include virtual network adapter **131-4** and virtual network adapter **131-5**, respectively. Virtual network adapter **131-4** and virtual network adapter **131-5** may couple to network adapter **116** via a channel. LPAR **128-6** and LPAR **128-7** may include virtual network adapter **131-6** and virtual network adapter **131-7**, respectively. Virtual network adapter **131-6** and virtual network adapter **131-7** may couple to network adapter **121** via a channel.

LPAR **128-1**, LPAR **128-2** and LPAR **128-3** may include virtual network adapter **132-1**, virtual network adapter **132-2** and virtual network adapter **132-3**, respectively. Virtual network adapter **132-1**, virtual network adapter **132-2** and virtual network adapter **132-3** may couple to network adapter **112** via a channel. LPAR **128-4** and LPAR **128-5** may include virtual network adapter **132-4** and virtual network adapter **132-5**, respectively. Virtual network adapter **132-4** and virtual network adapter **132-5** may couple to network adapter **117** via a channel. LPAR **128-6** and LPAR **128-7** may include virtual network adapter **132-6** and virtual network adapter **132-7**, respectively. Virtual network adapter **132-6** and virtual network adapter **132-7** may couple to network adapter **122** via a channel.

FIG. 2 depicts one embodiment of HCM database **200** in the disclosed HCM system **100**. HCM tool **600** may store the hardware configuration information in HCM database **200** on a per adapter basis. In one embodiment, for each network adapter in HCM system **100**, HCM tool **600** may store, from the leftmost column to the rightmost column, the machine serial number (MSN), physical identification (PID), logical identification (LID), adapter type, logical partition (LPAR) access list, physical network identification (PNet ID) for a first port of the network adapter, and the PNet ID for the second port of the network adapter.

In one embodiment, the machine serial number (MSN) may be a four byte hex value that identifies the IHS of the adapter. In one embodiment, the physical identification (PID) may be a physical channel ID (PCHID), i.e., the physical card slot in an I/O drawer of an IHS. In another embodiment, the PID may be a virtual channel identification (VCHID), a virtual ID given because internal adapters do not have a physical card slot in an IHS. In one embodiment, the logical identification (LID) may be a logical channel identification (CHPID). In another embodiment, the LID may be a function identification (FID), i.e. logical identification.

In one embodiment, the adapter type may be a two byte hex value that identifies the type of adapter. For example, OSA, RNIC and IQD adapters may be 0087, 0008, and 008D, respectively. In one embodiment, the logical partition (LPAR) access list may include eight one byte hex values that represent which LPARs in the IHS may access the particular adapter. In one embodiment, PNet ID 1 may include a four-

character string identifying the physical network coupled to the first port of the adapter. PNet ID 2 may include a four-character string identifying the physical network coupled to the second port of the adapter.

As shown in HCM database **200**, the hardware configuration information of adapter **111** includes MSN of 0000880B, PID of 0008, LID of 00F0, type of 0087, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **111** is located in physical channel 0008 in administered IHS **104** and may be identified logically by administered IHS **104** as 00F0. Adapter **111** is a physical OSA network adapter and couples to NETWORK A **113** on both ports 1 and 2. LPAR **128-1**, **128-2** and **128-3** of administered IHS **104** may access adapter **111** to communicate via NETWORK A **113**.

The hardware configuration information of adapter **112** includes MSN of 0000880B, PID of 0020, LID of 0200, type of 0008, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **112** is located in physical channel 0020 in administered IHS **104** and may be identified logically by administered IHS **104** as 0200. Adapter **112** is a physical RNIC network adapter and couples to NETWORK A **113** on both ports 1 and 2. LPAR **128-1**, **128-2** and **128-3** of administered IHS **104** may access adapter **112** to communicate via NETWORK A **113**.

The hardware configuration information of adapter **116** includes MSN of 0000880B, PID of 0009, LID of 00F4, type of 0087, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **116** is located in physical channel 0009 in administered IHS **104** and may be identified logically by administered IHS **104** as 00F4. Adapter **116** is a physical OSA network adapter and couples to NETWORK B **118** on both ports 1 and 2. LPAR **128-4** and **128-5** of administered IHS **104** may access adapter **116** to communicate via NETWORK B **118**.

The hardware configuration information of adapter **117** includes MSN of 0000880B, PID of 0021, LID of 0204, type of 0008, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **117** is located in physical channel 0021 in administered IHS **104** and may be identified logically by administered IHS **104** as 0204. Adapter **117** is a physical RNIC network adapter and couples to NETWORK B **118** on both ports 1 and 2. LPAR **128-4** and **128-5** of administered IHS **104** may access adapter **117** to communicate via NETWORK B **118**.

The hardware configuration information of adapter **121** includes MSN of 0000880B, PID of 020A, LID of 00F7, type of 0087, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **121** is located in physical channel 020A in administered IHS **104** and may be identified logically by administered IHS **104** as 00F7. Adapter **121** is a physical OSA network adapter and couples to NETWORK C **123** on both ports 1 and 2. LPAR **128-6** and **128-7** of administered IHS **104** may access adapter **121** to communicate via NETWORK C **123**.

The hardware configuration information of adapter **122** includes MSN of 0000880B, PID of 0222, LID of 0207, type of 0008, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **122** is located in physical channel 0222 in administered IHS **104** and may be identified logically by administered IHS **104** as 0207. Adapter **122** is a physical RNIC network adapter and couples to NETWORK C **123** on both ports 1 and 2. LPAR **128-6** and **128-7** of administered IHS **104** may access adapter **122** to communicate via NETWORK C **123**.

The hardware configuration information of adapter **129-1** includes MSN of 0000880B, PID of 0111, LID of 04C0, type

of 008D, LPAR access list of 01, 02, 03, 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 with no entries. In other words, adapter **129-1** is a virtual adapter with a virtual channel 0111 in administered IHS **104** and may be identified logically by administered IHS **104** as 04C0. Adapter **129-1** is an IQD virtual network adapter and couples to IQD network **130** on virtual channel 0111. LPAR **128-1, 128-2, 128-3, 128-4, 128-5, 128-6** and **128-7** of administered IHS **104** may access adapter **129-1** to communicate via IQD network **130**.

The hardware configuration information of adapter **129-2** includes MSN of 0000880B, PID of 0111, LID of 04C1, type of 008D, LPAR access list of 01, 02, 03, 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 with no entries. In other words, adapter **129-2** is a virtual adapter with a virtual channel 0111 in administered IHS **104** and may be identified logically by administered IHS **104** as 04C1. Adapter **129-2** is an IQD virtual network adapter and couples to IQD network **130** on virtual channel 0111. LPAR **128-1, 128-2, 128-3, 128-4, 128-5, 128-6** and **128-7** of administered IHS **104** may access adapter **129-2** to communicate via IQD network **130**.

The hardware configuration information of adapter **129-3** includes MSN of 0000880B, PID of 0111, LID of 04C2, type of 008D, LPAR access list of 01, 02, 03, 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 with no entries. In other words, adapter **129-3** is a virtual adapter with a virtual channel 0111 in administered IHS **104** and may be identified logically by administered IHS **104** as 04C2. Adapter **129-3** is an IQD virtual network adapter and couples to IQD network **130** on virtual channel 0111. LPAR **128-1, 128-2, 128-3, 128-4, 128-5, 128-6** and **128-7** of administered IHS **104** may access adapter **129-3** to communicate via IQD network **130**.

The hardware configuration information of adapter **129-4** includes MSN of 0000880B, PID of 0111, LID of 04C3, type of 008D, LPAR access list of 01, 02, 03, 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 with no entries. In other words, adapter **129-4** is a virtual adapter with a virtual channel 0111 in administered IHS **104** and may be identified logically by administered IHS **104** as 04C3. Adapter **129-4** is an IQD virtual network adapter and couples to IQD network **130** on virtual channel 0111. LPAR **128-1, 128-2, 128-3, 128-4, 128-5, 128-6** and **128-7** of administered IHS **104** may access adapter **129-4** to communicate via IQD network **130**.

The hardware configuration information of adapter **129-5** includes MSN of 0000880B, PID of 0111, LID of 04C4, type of 008D, LPAR access list of 01, 02, 03, 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 with no entries. In other words, adapter **129-5** is a virtual adapter with a virtual channel 0111 in administered IHS **104** and may be identified logically by administered IHS **104** as 04C4. Adapter **129-5** is an IQD virtual network adapter and couples to IQD network **130** on virtual channel 0111. LPAR **128-1, 128-2, 128-3, 128-4, 128-5, 128-6** and **128-7** of administered IHS **104** may access adapter **129-5** to communicate via IQD network **130**.

The hardware configuration information of adapter **129-6** includes MSN of 0000880B, PID of 0111, LID of 04C5, type of 008D, LPAR access list of 01, 02, 03, 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 with no entries. In other words, adapter **129-6** is a virtual adapter with a virtual channel 0111 in administered IHS **104** and may be identified logically by administered IHS **104** as 04C5. Adapter **129-6** is an IQD virtual network adapter and couples to IQD network **130** on virtual channel 0111. LPAR **128-1, 128-2, 128-3, 128-4, 128-5, 128-6** and **128-7** of administered IHS **104** may access adapter **129-6** to communicate via IQD network **130**.

The hardware configuration information of adapter **129-7** includes MSN of 0000880B, PID of 0111, LID of 04C6, type of 008D, LPAR access list of 01, 02, 03, 04, 05, 06 and 07, and

PNet ID 1 and PNet ID 2 with no entries. In other words, adapter **129-7** is a virtual adapter with a virtual channel 0111 in administered IHS **104** and may be identified logically by administered IHS **104** as 04C6. Adapter **129-7** is an IQD virtual network adapter and couples to IQD network **130** on virtual channel 0111. LPAR **128-1, 128-2, 128-3, 128-4, 128-5, 128-6** and **128-7** of administered IHS **104** may access adapter **129-7** to communicate via IQD network **130**.

The hardware configuration information of adapter **114** includes MSN of 8A0024FC, PID of 0007, LID of 0061, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **114** is located in physical channel 0007 in administered IHS **106** and may be identified logically by administered IHS **106** as 00B1. Adapter **114** is a physical OSA network adapter and couples to NETWORK A **113** on both ports 1 and 2. Administered IHS **106** may access adapter **114** to communicate via NETWORK A **113**.

The hardware configuration information of adapter **115** includes MSN of 8A0024FC, PID of 0012, LID of 0006, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **115** is located in physical channel 0012 in administered IHS **106** and may be identified logically by administered IHS **106** as 0006. Adapter **115** is a physical RNIC network adapter and couples to NETWORK A **113** on both ports 1 and 2. Administered IHS **106** may access adapter **115** to communicate via NETWORK A **113**.

The hardware configuration information of adapter **119** includes MSN of 578A7CE6, PID of 005A, LID of 0200, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **119** is located in physical channel 005A in administered IHS **108** and may be identified logically by administered IHS **108** as 0200. Adapter **119** is a physical OSA network adapter and couples to NETWORK B **118** on both ports 1 and 2. Administered IHS **108** may access adapter **119** to communicate via NETWORK B **118**.

The hardware configuration information of adapter **120** includes MSN of 578A7CE6, PID of 0402, LID of 001C, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **120** is located in physical channel 0402 in administered IHS **108** and may be identified logically by administered IHS **108** as 001C. Adapter **120** is a physical RNIC network adapter and couples to NETWORK B **118** on both ports 1 and 2. Administered IHS **108** may access adapter **115** to communicate via NETWORK B **118**.

The hardware configuration information of adapter **124** includes MSN of 578A7CE6, PID of 005B, LID of 0201, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **124** is located in physical channel 005B in administered IHS **108** and may be identified logically by administered IHS **108** as 0201. Adapter **124** is a physical OSA network adapter and couples to NETWORK C **123** on both ports 1 and 2. Administered IHS **108** may access adapter **124** to communicate via NETWORK C **123**.

The hardware configuration information of adapter **125** includes MSN of 578A7CE6, PID of 0444, LID of 001D, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **125** is located in physical channel 0444 in administered IHS **108** and may be identified logically by administered IHS **108** as 001D. Adapter **125** is a physical RNIC network adapter and couples

to NETWORK C 123 on both ports 1 and 2. Administered IHS 108 may access adapter 125 to communicate via NETWORK C 123.

The hardware configuration information of adapter 126 includes MSN of A453E85C, PID of 0002, LID of 0105, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter 126 is located in physical channel 0002 in administered IHS 110 and may be identified logically by administered IHS 110 as 0105. Adapter 126 is a physical OSA network adapter and couples to NETWORK C 123 on both ports 1 and 2. Administered IHS 110 may access adapter 126 to communicate via NETWORK C 123.

The hardware configuration information of adapter 127 includes MSN of A453E85C, PID of 0005, LID of 00A2, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter 127 is located in physical channel 0005 in administered IHS 110 and may be identified logically by administered IHS 110 as 00A2. Adapter 127 is a physical RNIC network adapter and couples to NETWORK C 123 on both ports 1 and 2. Administered IHS 110 may access adapter 127 to communicate via NETWORK C 123.

In one embodiment, HCM tool 600 in HCM IHS 500 may transmit the HCM database to a hypervisor agent of administered IHS 104, 106, 108 and/or 110 via administrative network 102. For example, the hypervisor agent of administered IHS 104 may receive HCM database 200 and allow the hypervisor of administered IHS 104 to extract hardware configuration information from HCM database 200. The hypervisor of administered IHS 104 may configure administered IHS 104 as shown in HCM database 200.

In one embodiment, a user may assign PNet ID, "NETA" to NETWORK A 113, "NETB" to NETWORK B 118, and "NETC" to NETWORK C 123, with HCM tool 600. A user may use HCM tool 600 to provision adapters 111, 112 for network A by assigning a PNet ID of "NETA" therewith. If more adapters are required due to bandwidth limitations between administered IHS 104 and NETWORK A 113, additional adapters may easily be provisioned by assigning a PNet ID of "NETA" to the adapter, with HCM tool 600.

FIG. 3 is a block diagram showing one embodiment of the disclosed hardware configuration management (HCM) system 300 utilizing physical network identifiers (PNet IDs). HCM system 300 may utilize network adapter 301, administrative network 302 and network adapter 303 to couple HCM IHS 500 to administered IHS 304. HCM system 300 may utilize network adapter 301, administrative network 302 and network adapter 305 to couple HCM IHS 500 to administered IHS 306. HCM system 300 may utilize network adapter 301, administrative network 302 and network adapter 307 to couple HCM IHS 500 to administered IHS 308. HCM system 300 may utilize network adapter 301, administrative network 302 and network adapter 309 to couple HCM IHS 500 to administered IHS 310. Administered IHSs 304, 306, 308 and 310 couple via administrative network 302 to HCM IHS 500 to enable HCM IHS 500 to administer HCM database 400 with HCM tool 600 to the administered IHSs.

HCM system 300 may utilize network adapter 311 and/or network adapter 312 and/or network adapter 313 and/or network adapter 314 via NETWORK A 315 via network adapter 316 and/or network adapter 317 to couple administered IHS 304 to administered IHS 306. HCM system 300 may utilize network adapter 318 and/or network adapter 319 and/or network adapter 320 and/or network adapter 321 via NETWORK B 322 via network adapter 323 and/or network adapter 324 to couple administered IHS 304 to administered

IHS 306. HCM system 300 may utilize network adapter 318 and/or network adapter 319 and/or network adapter 320 and/or network adapter 321 via NETWORK B 322 via network adapter 325 and/or network adapter 326 to couple administered IHS 304 to administered IHS 308. HCM system 300 may utilize network adapter 327 and/or network adapter 328 and/or network adapter 329 and/or network adapter 330 via NETWORK C 331 via network adapter 332 and/or network adapter 333 to couple administered IHS 304 to administered IHS 308. HCM system 300 may utilize network adapter 327 and/or network adapter 328 and/or network adapter 329 and/or network adapter 330 via NETWORK C 331 via network adapter 334 and/or network adapter 335 and/or network adapter 336 and/or network adapter 337 to couple administered IHS 304 to administered IHS 310.

In one embodiment, network adapter 301, 303, 305, 307 and 309 may be Ethernet (ETH) adapters. Network adapters 311, 312, 316, 318, 319, 323, 325, 327, 328, 334 and 336 may be open system adapters (OSAs). Network adapters 313, 314, 317, 320, 321, 326, 329, 330, 333, 335 and 337 may be remote direct memory access (RDMA) enabled network adapter controllers (RNICs). In one embodiment, administrative network 302, NETWORK A 315, NETWORK B 322 and NETWORK C 331 may provide local area network (LAN) communications and/or wide area network (WAN) communications and/or virtual LAN communications and/or intranet communications and/or Internet communications to structures that couple thereto.

Administered IHS 304 may include a hypervisor (not shown) that may create logical partition (LPAR) 338-1, LPAR 338-2, LPAR 338-3, LPAR 338-4, LPAR 338-5, LPAR 338-6 and LPAR 338-7 in administered IHS 304. LPAR 338-1, LPAR 338-2, LPAR 338-3, LPAR 338-4, LPAR 338-5, LPAR 338-6 and LPAR 338-7 may respectively include virtual internal network adapter 339-1, virtual internal network adapter 339-2, virtual internal network adapter 339-3, virtual internal network adapter 339-4, virtual internal network adapter 339-5, virtual internal network adapter 339-6 and virtual internal network adapter 339-7. Virtual internal network adapter 339-1, 339-2, 339-3, 339-4, 339-5, 339-6 and 339-7 may be internal queued direct (IQD) communication adapters and couple to one another via administered IHS 304 IQD network 340. Administered IHS 304 IQD network 340 may be a channel, i.e., a bus.

LPAR 338-1, LPAR 338-2 and LPAR 338-3 may include virtual network adapter 341-1, virtual network adapter 341-2 and virtual network adapter 341-3, respectively. Virtual network adapter 341-1, virtual network adapter 341-2 and virtual network adapter 341-3 may couple to network adapter 311 and network adapter 312 via a channel. LPAR 338-4 and LPAR 338-5 may include virtual network adapter 341-4 and virtual network adapter 341-5, respectively. Virtual network adapter 341-4 and virtual network adapter 341-5 may couple to network adapter 318 and network adapter 319 via a channel. LPAR 338-6 and LPAR 338-7 may include virtual network adapter 341-6 and virtual network adapter 341-7, respectively. Virtual network adapter 341-6 and virtual network adapter 341-7 may couple to network adapter 327 and network adapter 328 via a channel.

LPAR 338-1, LPAR 338-2 and LPAR 338-3 may include virtual network adapter 342-1, virtual network adapter 342-2 and virtual network adapter 342-3, respectively. Virtual network adapter 342-1, virtual network adapter 342-2 and virtual network adapter 342-3 may couple to network adapter 313 and network adapter 314 via a channel. LPAR 338-4 and LPAR 338-5 may include virtual network adapter 342-4 and virtual network adapter 342-5, respectively. Virtual network

11

adapter **342-4** and virtual network adapter **342-5** may couple to network adapter **320** and network adapter **321** via a channel. LPAR **338-6** and LPAR **338-7** may include virtual network adapter **342-6** and virtual network adapter **342-7**, respectively. Virtual network adapter **342-6** and virtual network adapter **342-7** may couple to network adapter **329** and network adapter **330** via a channel.

FIG. 4 depicts one embodiment of HCM database **400** in the disclosed HCM system **300**. HCM tool **600** may store the hardware configuration information in HCM database **400** on a per adapter basis. In one embodiment, for each network adapter in HCM system **300**, HCM tool **600** may store, from the leftmost column to the rightmost column, the machine serial number (MSN), physical identification (PID), logical identification (LID), adapter type, logical partition (LPAR) access list, physical network identification (PNet ID) for a first port of the network adapter, and the PNet ID for the second port of the network adapter.

As shown in HCM database **400**, the hardware configuration information of adapter **311** includes MSN of 000F880A, PID of 0008, LID of 00F0, type of 0087, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **311** is located in physical channel 0008 in administered IHS **304** and may be identified logically by administered IHS **304** as 00F0. Adapter **311** is a physical OSA network adapter and couples to NETWORK A **315** on both ports 1 and 2. LPAR **338-1**, **338-2** and **338-3** of administered IHS **304** may access adapter **311** to communicate via NETWORK A **315**.

The hardware configuration information of adapter **312** includes MSN of 000F880A, PID of 0009, LID of 00F1, type of 0087, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **312** is located in physical channel 0009 in administered IHS **304** and may be identified logically by administered IHS **304** as 00F1. Adapter **312** is a physical OSA network adapter and couples to NETWORK A **315** on both ports 1 and 2. LPAR **338-1**, **338-2** and **338-3** of administered IHS **304** may access adapter **312** to communicate via NETWORK A **315**.

The hardware configuration information of adapter **313** includes MSN of 000F880A, PID of 020A, LID of 0010, type of 0008, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **313** is located in physical channel 020A in administered IHS **304** and may be identified logically by administered IHS **304** as 0010. Adapter **313** is a physical RNIC network adapter and couples to NETWORK A **315** on both ports 1 and 2. LPAR **338-1**, **338-2** and **338-3** of administered IHS **304** may access adapter **313** to communicate via NETWORK A **315**.

The hardware configuration information of adapter **314** includes MSN of 000F880A, PID of 020B, LID of 0011, type of 0008, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **314** is located in physical channel 020B in administered IHS **304** and may be identified logically by administered IHS **304** as 0011. Adapter **314** is a physical RNIC network adapter and couples to NETWORK A **315** on both ports 1 and 2. LPAR **338-1**, **338-2** and **338-3** of administered IHS **304** may access adapter **314** to communicate via NETWORK A **315**.

The hardware configuration information of adapter **318** includes MSN of 000F880A, PID of 0330, LID of 00F5, type of 0087, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **318** is located in physical channel 0330 in administered IHS **304** and may be identified logically by administered IHS **304** as 00F5. Adapter **318** is a physical OSA network adapter and couples to NETWORK B **322** on both ports 1 and 2. LPAR **338-4** and

12

338-5 of administered IHS **304** may access adapter **318** to communicate via NETWORK B **322**.

The hardware configuration information of adapter **319** includes MSN of 000F880A, PID of 0331, LID of 00F6, type of 0087, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **319** is located in physical channel 0331 in administered IHS **304** and may be identified logically by administered IHS **304** as 00F6. Adapter **319** is a physical OSA network adapter and couples to NETWORK B **322** on both ports 1 and 2. LPAR **338-4** and **338-5** of administered IHS **304** may access adapter **319** to communicate via NETWORK B **322**.

The hardware configuration information of adapter **320** includes MSN of 000F880A, PID of 020C, LID of 0015, type of 0008, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **320** is located in physical channel 020C in administered IHS **304** and may be identified logically by administered IHS **304** as 0015. Adapter **320** is a physical RNIC network adapter and couples to NETWORK B **322** on both ports 1 and 2. LPAR **338-4** and **338-5** of administered IHS **304** may access adapter **320** to communicate via NETWORK B **322**.

The hardware configuration information of adapter **321** includes MSN of 000F880A, PID of 020D, LID of 0016, type of 0008, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **321** is located in physical channel 020D in administered IHS **304** and may be identified logically by administered IHS **304** as 0016. Adapter **321** is a physical RNIC network adapter and couples to NETWORK B **322** on both ports 1 and 2. LPAR **338-4** and **338-5** of administered IHS **304** may access adapter **321** to communicate via NETWORK B **322**.

The hardware configuration information of adapter **327** includes MSN of 000F880A, PID of 0111, LID of 00F9, type of 0087, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **327** is located in physical channel 0111 in administered IHS **304** and may be identified logically by administered IHS **304** as 00F9. Adapter **327** is a physical OSA network adapter and couples to NETWORK C **331** on both ports 1 and 2. LPAR **338-6** and **338-7** of administered IHS **304** may access adapter **327** to communicate via NETWORK C **331**.

The hardware configuration information of adapter **328** includes MSN of 000F880A, PID of 0112, LID of 00FA, type of 0087, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **328** is located in physical channel 0112 in administered IHS **304** and may be identified logically by administered IHS **304** as 00FA. Adapter **328** is a physical OSA network adapter and couples to NETWORK C **331** on both ports 1 and 2. LPAR **338-6** and **338-7** of administered IHS **304** may access adapter **328** to communicate via NETWORK C **331**.

The hardware configuration information of adapter **329** includes MSN of 000F880A, PID of 020E, LID of 0019, type of 0008, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **329** is located in physical channel 020E in administered IHS **304** and may be identified logically by administered IHS **304** as 0019. Adapter **329** is a physical RNIC network adapter and couples to NETWORK C **331** on both ports 1 and 2. LPAR **338-6** and **338-7** of administered IHS **304** may access adapter **329** to communicate via NETWORK C **331**.

The hardware configuration information of adapter **330** includes MSN of 000F880A, PID of 020F, LID of 0020, type of 0008, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **330** is located in physical channel 020F in administered IHS **304** and may be

13

identified logically by administered IHS 304 as 0020. Adapter 330 is a physical RNIC network adapter and couples to NETWORK C 331 on both ports 1 and 2. LPAR 338-6 and 338-7 of administered IHS 304 may access adapter 330 to communicate via NETWORK C 331.

The hardware configuration information of adapter 339-1 includes MSN of 000F880A, PID of 0222, LID of 06D0, type of 008D, LPAR access list of 01, 02, 03, 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 with no entries. In other words, adapter 339-1 is a virtual adapter with a virtual channel 0222 in administered IHS 304 and may be identified logically by administered IHS 304 as 06D0. Adapter 339-1 is an IQD virtual network adapter and couples to IQD network 340 on virtual channel 0222. LPAR 338-1, 338-2, 338-3, 338-4, 338-5, 338-6 and 338-7 of administered IHS 304 may access adapter 339-1 to communicate via IQD network 340.

The hardware configuration information of adapter 339-2 includes MSN of 000F880A, PID of 0222, LID of 06D1, type of 008D, LPAR access list of 01, 02, 03, 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 with no entries. In other words, adapter 339-2 is a virtual adapter with a virtual channel 0222 in administered IHS 304 and may be identified logically by administered IHS 304 as 06D1. Adapter 339-2 is an IQD virtual network adapter and couples to IQD network 340 on virtual channel 0222. LPAR 338-1, 338-2, 338-3, 338-4, 338-5, 338-6 and 338-7 of administered IHS 304 may access adapter 339-2 to communicate via IQD network 340.

The hardware configuration information of adapter 339-3 includes MSN of 000F880A, PID of 0222, LID of 06D2, type of 008D, LPAR access list of 01, 02, 03, 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 with no entries. In other words, adapter 339-3 is a virtual adapter with a virtual channel 0222 in administered IHS 304 and may be identified logically by administered IHS 304 as 06D2. Adapter 339-3 is an IQD virtual network adapter and couples to IQD network 340 on virtual channel 0222. LPAR 338-1, 338-2, 338-3, 338-4, 338-5, 338-6 and 338-7 of administered IHS 304 may access adapter 339-3 to communicate via IQD network 340.

The hardware configuration information of adapter 339-4 includes MSN of 000F880A, PID of 0222, LID of 06D3, type of 008D, LPAR access list of 01, 02, 03, 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 with no entries. In other words, adapter 339-4 is a virtual adapter with a virtual channel 0222 in administered IHS 304 and may be identified logically by administered IHS 304 as 06D3. Adapter 339-4 is an IQD virtual network adapter and couples to IQD network 340 on virtual channel 0222. LPAR 338-1, 338-2, 338-3, 338-4, 338-5, 338-6 and 338-7 of administered IHS 304 may access adapter 339-4 to communicate via IQD network 340.

The hardware configuration information of adapter 339-5 includes MSN of 000F880A, PID of 0222, LID of 06D4, type of 008D, LPAR access list of 01, 02, 03, 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 with no entries. In other words, adapter 339-5 is a virtual adapter with a virtual channel 0222 in administered IHS 304 and may be identified logically by administered IHS 304 as 06D4. Adapter 339-5 is an IQD virtual network adapter and couples to IQD network 340 on virtual channel 0222. LPAR 338-1, 338-2, 338-3, 338-4, 338-5, 338-6 and 338-7 of administered IHS 304 may access adapter 339-5 to communicate via IQD network 340.

The hardware configuration information of adapter 339-6 includes MSN of 000F880A, PID of 0222, LID of 06D5, type of 008D, LPAR access list of 01, 02, 03, 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 with no entries. In other words, adapter 339-6 is a virtual adapter with a virtual channel 0222 in administered IHS 304 and may be identified logically by administered IHS 304 as 06D5. Adapter 339-6 is an IQD

14

virtual network adapter and couples to IQD network 340 on virtual channel 0222. LPAR 338-1, 338-2, 338-3, 338-4, 338-5, 338-6 and 338-7 of administered IHS 304 may access adapter 339-6 to communicate via IQD network 340.

The hardware configuration information of adapter 339-7 includes MSN of 000F880A, PID of 0222, LID of 06D6, type of 008D, LPAR access list of 01, 02, 03, 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 with no entries. In other words, adapter 339-7 is a virtual adapter with a virtual channel 0222 in administered IHS 304 and may be identified logically by administered IHS 304 as 06D6. Adapter 339-7 is an IQD virtual network adapter and couples to IQD network 340 on virtual channel 0222. LPAR 338-1, 338-2, 338-3, 338-4, 338-5, 338-6 and 338-7 of administered IHS 304 may access adapter 339-7 to communicate via IQD network 340.

The hardware configuration information of adapter 316 includes MSN of A467E85D, PID of 0005, LID of 00D1, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter 316 is located in physical channel 0005 in administered IHS 306 and may be identified logically by administered IHS 306 as 00D1. Adapter 316 is a physical OSA network adapter and couples to NETWORK A 315 on both ports 1 and 2. Administered IHS 306 may access adapter 316 to communicate via NETWORK A 315.

The hardware configuration information of adapter 317 includes MSN of A467E85D, PID of 0016, LID of 0CB1, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter 317 is located in physical channel 0016 in administered IHS 306 and may be identified logically by administered IHS 306 as 0CB1. Adapter 317 is a physical RNIC network adapter and couples to NETWORK A 315 on both ports 1 and 2. Administered IHS 306 may access adapter 317 to communicate via NETWORK A 315.

The hardware configuration information of adapter 323 includes MSN of A467E85D, PID of 0006, LID of 00D2, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter 323 is located in physical channel 0006 in administered IHS 306 and may be identified logically by administered IHS 306 as 00D2. Adapter 323 is a physical OSA network adapter and couples to NETWORK B 322 on both ports 1 and 2. Administered IHS 306 may access adapter 323 to communicate via NETWORK B 322.

The hardware configuration information of adapter 324 includes MSN of A467E85D, PID of 0017, LID of 0CB2, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter 324 is located in physical channel 0017 in administered IHS 306 and may be identified logically by administered IHS 306 as 0CB2. Adapter 324 is a physical RNIC network adapter and couples to NETWORK B 322 on both ports 1 and 2. Administered IHS 306 may access adapter 324 to communicate via NETWORK B 322.

The hardware configuration information of adapter 325 includes MSN of 007A0052, PID of 00A1, LID of 00F0, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter 325 is located in physical channel 00A1 in administered IHS 308 and may be identified logically by administered IHS 308 as 00F0. Adapter 325 is a physical OSA network adapter and couples to NETWORK B 322 on both ports 1 and 2. Administered IHS 308 may access adapter 325 to communicate via NETWORK B 322.

The hardware configuration information of adapter 326 includes MSN of 007A0052, PID of 00D1, LID of 00F1, type

15

of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **326** is located in physical channel 00D1 in administered IHS **308** and may be identified logically by administered IHS **308** as 00F1. Adapter **326** is a physical RNIC network adapter and couples to NETWORK B **322** on both ports 1 and 2. Administered IHS **308** may access adapter **326** to communicate via NETWORK B **322**.

The hardware configuration information of adapter **332** includes MSN of 007A0052, PID of 00A2, LID of 00F2, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **332** is located in physical channel 00A2 in administered IHS **308** and may be identified logically by administered IHS **308** as 00F2. Adapter **332** is a physical OSA network adapter and couples to NETWORK C **331** on both ports 1 and 2. Administered IHS **308** may access adapter **332** to communicate via NETWORK C **331**.

The hardware configuration information of adapter **333** includes MSN of 007A0052, PID of 00D2, LID of 00F3, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **333** is located in physical channel 00D2 in administered IHS **308** and may be identified logically by administered IHS **308** as 00F3. Adapter **333** is a physical RNIC network adapter and couples to NETWORK C **331** on both ports 1 and 2. Administered IHS **308** may access adapter **333** to communicate via NETWORK C **331**.

The hardware configuration information of adapter **334** includes MSN of C6200070, PID of 0016, LID of 00CA, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **334** is located in physical channel 0016 in administered IHS **310** and may be identified logically by administered IHS **310** as 00CA. Adapter **334** is a physical OSA network adapter and couples to NETWORK C **331** on both ports 1 and 2. Administered IHS **310** may access adapter **334** to communicate via NETWORK C **331**.

The hardware configuration information of adapter **335** includes MSN of C6200070, PID of 0032, LID of 00CB, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **335** is located in physical channel 0032 in administered IHS **310** and may be identified logically by administered IHS **310** as 00CB. Adapter **335** is a physical RNIC network adapter and couples to NETWORK C **331** on both ports 1 and 2. Administered IHS **310** may access adapter **335** to communicate via NETWORK C **331**.

The hardware configuration information of adapter **336** includes MSN of C6200070, PID of 0022, LID of 00CC, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **336** is located in physical channel 0022 in administered IHS **310** and may be identified logically by administered IHS **310** as 00CC. Adapter **336** is a physical OSA network adapter and couples to NETWORK C **331** on both ports 1 and 2. Administered IHS **310** may access adapter **336** to communicate via NETWORK C **331**.

The hardware configuration information of adapter **337** includes MSN of C6200070, PID of 000A, LID of 00CD, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **337** is located in physical channel 000A in administered IHS **310** and may be identified logically by administered IHS **310** as 00CD. Adapter **337** is a physical RNIC network adapter and

16

couples to NETWORK C **331** on both ports 1 and 2. Administered IHS **310** may access adapter **337** to communicate via NETWORK C **331**.

In one embodiment, HCM tool **600** in HCM IHS **500** may transmit the HCM database to a hypervisor agent of administered IHS **104**, **106**, **108** and/or **110** via administrative network **102**. For example, the hypervisor agent of administered IHS **104** may receive HCM database **200** and allow the hypervisor of administered IHS **104** to extract hardware configuration information from HCM database **400**. The hypervisor of administered IHS **104** may configure administered IHS **104** as shown in HCM database **400**.

FIG. 5 is a block diagram of an HCM information handling system (IHS) **500** that may be used in the disclosed HCM system. HCM IHS **500** includes a processor **505** that may include multiple cores. HCM IHS **500** processes, transfers, communicates, modifies, stores or otherwise handles information in digital form, analog form or other form. HCM IHS **500** includes a bus **510** that couples processor **505** to memory **515** via a memory controller **520** and memory bus **525**. System memory **515** may also be referred to as main memory. System memory **515** may be a static random access memory (SRAM) array or a dynamic random access memory (DRAM) array. Processor **505** may also include local memory such as L1, L2 and L3 caches. A video graphics controller **530** couples display **535** to bus **510**. Nonvolatile storage **540**, such as a hard disk drive, solid-state drive (SSD), CD drive, DVD drive, or other nonvolatile storage couples to bus **510** to provide HCM IHS **500** with permanent storage of information. System memory **515** and nonvolatile storage **540** are both forms of memory stores. Nonvolatile storage **540** stores an operating system **545** (OPERATING SYS) that governs operation of HCM IHS **500**. I/O devices **550**, such as speakers, a keyboard and a pointing device, couple to bus **510** via I/O controller **555** and I/O bus **560**.

One or more expansion busses **565**, such as USB, IEEE 1394 bus, ATA, SATA, PCI, PCIE, DVI, HDMI and other busses, couple to bus **510** to facilitate the connection of peripherals and devices to HCM IHS **500**. A network interface controller (NIC) **570** couples to bus **510** to enable HCM IHS **500** to connect by wire or wirelessly to a network and other information handling systems. NIC **570** may also be called a network communication adapter, network interface adapter, network adapter, network interface or an adapter. NIC **570** may take many forms. For example, NIC **570** may take the form of an Ethernet (ETH) adapter, open systems adapter (OSA), RDMA enabled network interface controller (RN IC) or other network communication adapter.

While FIG. 5 shows one IHS that employs processor **505**, the IHS may take many forms. For example, HCM IHS **500** may take the form of a desktop, portable, laptop, notebook, tablet or other form factor computer or data processing system. HCM IHS **500** may take other form factors such as a gaming device, a personal digital assistant (PDA), a portable telephone device, a communication device or other devices that include a processor and memory.

HCM IHS **500** includes a hardware configuration management (HCM) tool computer program product **600** on digital media **575** such as a CD, DVD or other media. For simplicity, the term HCM tool will be used below. HCM IHS **500** may store HCM tool **600** in nonvolatile storage **540** as HCM tool **600**. HCM IHS **500** may also store operating system **545** (OPERATING SYS) and HCM database **580** in nonvolatile storage **540**. When HCM IHS **500** initializes, the IHS loads operating system **545** into system memory **515** for execution as operating system **545**. HCM IHS **500** also loads HCM

database 580 and HCM tool 600 into system memory 515 for execution as HCM database 580' and HCM tool 600", respectively.

FIG. 6 is a flowchart that shows a representative process flow of an HCM tool 600 that may be used in the disclosed HCM system. Process flow commences when HCM tool 600 in HCM IHS 500 initializes, as per block 605. The HCM tool 600 may determine if HCM database 580 exists in HCM IHS 500, as per block 610. If HCM database 580 exists in HCM IHS 500, HCM tool 600 opens HCM database 580 for modification, as per block 615. However, if HCM database 580 does not exist in HCM IHS 500, HCM tool 600 generates a blank HCM database 580 in HCM IHS 500 and opens the HCM database 580 for modification, as per block 620.

HCM database 580 may store entries on a per adapter basis, i.e., each row in HCM database 580 may contain information that pertains to a specific network adapter. Process flow continues as HCM tool 600 checks the entries in HCM database 580 and determines if rows in HCM database 580 are assigned physical network identifications (PNet IDs), as per block 625. If HCM tool 600 determines that rows of HCM database 580 have not been assigned PNet IDs, HCM tool 600 may generate a PNet ID and assign the particular PNet ID to a particular physical network and store the generated PNet IDs in HCM database 580, as per block 630. For example, HCM tool 600 may generate a PNet ID of "NETA" for NETWORK A 113, "NETB" for NETWORK B 118, and/or "NETC" for NETWORK C 123. In one embodiment, a user may input PNet IDs to the HCM tool 600 and the user may assign particular PNet IDs to particular physical networks with HCM tool 600.

HCM tool 600 may provision the network adapters of each administered IHS in the HCM system. HCM tool 600 may modify rows of HCM database 580 to include logical partition (LPAR) designations of LPARs in the particular administered IHS that may access each particular network adapter, as per block 635. For example, HCM tool 600 may provision LPARs 01, 02, and 03 of administered IHS 104 to utilize network adapter 111, as shown in the first row of HCM database 200 in FIG. 2, i.e., the hardware configuration information related to network adapter 111. In one embodiment, a user may utilize the HCM tool 600 to provision the network adapters of each administered IHS in the HCM system. The user may input LPAR designations of LPARs in the particular administered IHS that may access each particular network adapter, to the HCM tool 600. The HCM tool 600 may modify the rows of HCM database 580 to include the LPAR designations of LPARs in the particular administered IHS that may access each particular network adapter.

HCM tool 600 may then assign PNet IDs to the network adapters of each administered IHS in the HCM system. HCM tool 600 may modify rows of HCM database 580 to include PNet IDs of the physical networks to which the particular network adapters connect, as per block 640. For example, as shown in FIG. 1, since both ports of network adapter 111 physically connect to NETWORK A 113, HCM tool 600 may assign PNet ID "NETA" to both ports of network adapter 111, by storing, "NETA" in the first row, "PNET ID1" column of HCM database 200 and by storing, "NETA" in the first row, "PNET ID2" column of HCM database 200. In one embodiment, a user may utilize the HCM tool 600 to assign PNet IDs to network adapters of each administered IHS in the HCM system. The user may input and/or select PNet IDs with HCM tool 600 and assign the PNet IDs to particular network adapters with HCM tool 600. The HCM tool 600 may then modify the rows of HCM database 580 to include the assigned PNet IDs with the particular network adapter.

If HCM tool 600 determines that rows of HCM database 580 have been assigned PNet IDs, as per block 625, process flow continues at block 645. HCM tool 600 inspects the configuration of the HCM system that may include the machine serial number (MSN), physical identification (PID), logical identification (LID), type, LPAR access list, PNet ID1 and PNet ID2 on a per adapter basis, as per block 645. HCM tool 600 may also inspect the hardware configuration information of each network adapter in HCM database 580.

If HCM tool 600 determines that the HCM system configuration does not match HCM database 580, as per block 650, HCM tool 600 updates the information stored in HCM database 580 with the inspected configuration of the HCM system, as per block 655. In one embodiment, a user may view HCM database 580 with HCM tool 600 and determine if HCM database 580 matches the HCM system configuration. If HCM database 580 does not match the HCM system configuration, the user may input the HCM system configuration to the HCM tool 600. HCM tool 600 may then store the HCM system configuration input by the user to HCM database 580.

If HCM tool 600 determines that the HCM system configuration does match HCM database 580, as per block 650, process flow continues at block 660. If HCM tool 600 determines that HCM database 580 has been modified and/or generated, as per block 660, HCM tool 600 may transmit HCM database 580 to any or all administered IHSs, as per block 665. For example, as shown in FIG. 1, HCM tool 600 may transmit HCM database 200 to administered IHS 104, 106, 108 and/or 110 via administrative network 102. In one embodiment, a user may input or select a transmit command in HCM tool 600, causing HCM tool 600 to transmit HCM database 580 to any or all administered IHSs. In another embodiment HCM tool 600 may transmit HCM database 580 to any or all administered IHSs at a user specified time interval. If HCM tool 600 determines that the HCM database 580 has not been modified and/or generated, as per block 660, process flow continues at block 670. Process flow terminates at end block 670. Alternatively, process flow may continue at start block 605.

II. RNIC Converging System

FIG. 7 is a block diagram showing one embodiment of the disclosed remote direct memory access (RDMA) enabled network adapter controller (RNIC) converging system 700 utilizing PNet IDs. RNIC converging system 700 may utilize network adapter 701, administrative network 702 and network adapter 703 to couple HCM IHS 500 to administered IHS 704. Administered IHS 704 may also be referred to as RNIC converging IHS 704. RNIC converging system 700 may utilize network adapter 701, administrative network 702 and network adapter 705 to couple HCM IHS 500 to administered IHS 706. RNIC converging system 700 may utilize network adapter 701, administrative network 702 and network adapter 707 to couple HCM IHS 500 to administered IHS 708. RNIC converging system 700 may utilize network adapter 701, administrative network 702 and network adapter 709 to couple HCM IHS 500 to administered IHS 710. Administered IHSs 704, 706, 708 and 710 couple via administrative network 702 to HCM IHS 500 to enable HCM IHS 500 to administer HCM database 800 with HCM tool 600 to the administered IHSs.

RNIC converging system 700 may utilize network adapter 711 and/or network adapter 712 via NETWORK A 713 via network adapter 714 and/or network adapter 715 to couple RNIC converging IHS 704 to administered IHS 706. RNIC converging system 700 may utilize network adapter 716 and/or network adapter 717 via NETWORK B 718 via network adapter 719 and/or network adapter 720 to couple RNIC

converging IHS 704 to administered IHS 708. RNIC converging system 700 may utilize network adapter 721 and/or network adapter 722 via NETWORK C 723 via network adapter 724 and/or network adapter 725 to couple RNIC converging IHS 704 to administered IHS 708. RNIC converging system 700 may utilize network adapter 721 and/or network adapter 722 via NETWORK C 723 via network adapter 726 to couple RNIC converging IHS 704 to administered IHS 710.

In one embodiment, network adapter 701, 703, 705, 707 and 709 may be Ethernet (ETH) adapters. Network adapters 711, 714, 716, 719, 721, 724 and 726 may be open system adapters (OSAs). Network adapters 712, 715, 717, 720, 722 and 725 may be remote direct memory access (RDMA) enabled network adapter controllers (RNICs). In one embodiment, administrative network 702, NETWORK A 713, NETWORK B 718 and NETWORK C 723 may provide local area network (LAN) communications and/or wide area network (WAN) communications and/or virtual LAN communications and/or intranet communications and/or Internet communications to structures that couple thereto.

RNIC converging IHS 704 may include a hypervisor (not shown) that may create logical partition (LPAR) 727-1, LPAR 727-2, LPAR 727-3, LPAR 727-4, LPAR 727-5, LPAR 727-6 and LPAR 727-7 in RNIC converging IHS 704. LPAR 727-1, LPAR 727-2 and LPAR 727-3 may include virtual network adapter 728-1, virtual network adapter 728-2 and virtual network adapter 728-3, respectively. Virtual network adapter 728-1, virtual network adapter 728-2 and virtual network adapter 728-3 may couple to network adapter 711 via a channel, i.e., a bus. LPAR 727-4 and LPAR 727-5 may include virtual network adapter 728-4 and virtual network adapter 728-5, respectively. Virtual network adapter 728-4 and virtual network adapter 728-5 may couple to network adapter 716 via a channel. LPAR 727-6 and LPAR 727-7 may include virtual network adapter 728-6 and virtual network adapter 728-7, respectively. Virtual network adapter 728-6 and virtual network adapter 728-7 may couple to network adapter 721 via a channel.

LPAR 727-1, LPAR 727-2 and LPAR 727-3 may include virtual network adapter 729-1, virtual network adapter 729-2 and virtual network adapter 729-3, respectively. Virtual network adapter 729-1, virtual network adapter 729-2 and virtual network adapter 729-3 may couple to network adapter 712 via a channel. LPAR 727-4 and LPAR 727-5 may include virtual network adapter 729-4 and virtual network adapter 729-5, respectively. Virtual network adapter 729-4 and virtual network adapter 729-5 may couple to network adapter 717 via a channel. LPAR 727-6 and LPAR 727-7 may include virtual network adapter 729-6 and virtual network adapter 729-7, respectively. Virtual network adapter 729-6 and virtual network adapter 729-7 may couple to network adapter 722 via a channel.

FIG. 8 depicts one embodiment of HCM database 800 in the disclosed RNIC converging system 700. HCM tool 600 may store the hardware configuration information in HCM database 800 on a per adapter basis. In one embodiment, for each network adapter in RNIC converging system 700, HCM tool 600 may store, from the leftmost column to the rightmost column, the machine serial number (MSN), physical identification (PID), logical identification (LID), adapter type, logical partition (LPAR) access list, physical network identification (PNet ID) for a first port of the network adapter, and the PNet ID for the second port of the network adapter.

As shown in HCM database 800, the hardware configuration information of adapter 711 includes MSN of 00D5380C, PID of 0008, LID of 00F0, type of 0087, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other

words, adapter 711 is located in physical channel 0008 in RNIC converging IHS 704 and may be identified logically by RNIC converging IHS 704 as 00F0. Adapter 711 is a physical OSA network adapter and couples to NETWORK A 713 on both ports 1 and 2. LPAR 727-1, 727-2 and 727-3 of RNIC converging IHS 704 may access adapter 711 to communicate via NETWORK A 713.

The hardware configuration information of adapter 712 includes MSN of 00D5380C, PID of 0009, LID of 02F0, type of 0008, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter 712 is located in physical channel 0009 in RNIC converging IHS 704 and may be identified logically by RNIC converging IHS 704 as 02F0. Adapter 712 is a physical RNIC network adapter and couples to NETWORK A 713 on both ports 1 and 2. LPAR 727-1, 727-2 and 727-3 of RNIC converging IHS 704 may access adapter 712 to communicate via NETWORK A 713.

The hardware configuration information of adapter 716 includes MSN of 00D5380C, PID of 020A, LID of 00F4, type of 0087, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter 716 is located in physical channel 020A in RNIC converging IHS 704 and may be identified logically by RNIC converging IHS 704 as 00F4. Adapter 716 is a physical OSA network adapter and couples to NETWORK B 718 on both ports 1 and 2. LPAR 727-4 and 727-5 of RNIC converging IHS 704 may access adapter 716 to communicate via NETWORK B 718.

The hardware configuration information of adapter 717 includes MSN of 00D5380C, PID of 020B, LID of 02F4, type of 0008, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter 717 is located in physical channel 020B in RNIC converging IHS 704 and may be identified logically by RNIC converging IHS 704 as 02F4. Adapter 717 is a physical RNIC network adapter and couples to NETWORK B 718 on both ports 1 and 2. LPAR 727-4 and 727-5 of RNIC converging IHS 704 may access adapter 717 to communicate via NETWORK B 718.

The hardware configuration information of adapter 721 includes MSN of 00D5380C, PID of 0330, LID of 00F7, type of 0087, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter 721 is located in physical channel 0330 in RNIC converging IHS 704 and may be identified logically by RNIC converging IHS 704 as 00F7. Adapter 721 is a physical OSA network adapter and couples to NETWORK C 723 on both ports 1 and 2. LPAR 727-6 and 727-7 of RNIC converging IHS 704 may access adapter 721 to communicate via NETWORK C 723.

The hardware configuration information of adapter 722 includes MSN of 00D5380C, PID of 0331, LID of 02F7, type of 0008, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter 722 is located in physical channel 0331 in RNIC converging IHS 704 and may be identified logically by RNIC converging IHS 704 as 02F7. Adapter 722 is a physical RNIC network adapter and couples to NETWORK C 723 on both ports 1 and 2. LPAR 727-6 and 727-7 of RNIC converging IHS 704 may access adapter 722 to communicate via NETWORK C 723.

The hardware configuration information of adapter 714 includes MSN of 0007880A, PID of 020C, LID of 0022, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter 714 is located in physical channel 020C in administered IHS 706 and may be identified logically by administered IHS 706 as 0022. Adapter 714 is a physical OSA network adapter and couples to NETWORK A 713 on both ports 1 and 2. Administered IHS 706 may access adapter 714 to communicate via NETWORK A 713.

21

The hardware configuration information of adapter **715** includes MSN of 0007880A, PID of 020D, LID of 0023, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **715** is located in physical channel 020D in administered IHS **706** and may be identified logically by administered IHS **706** as **0023**. Adapter **715** is a physical RNIC network adapter and couples to NETWORK A **713** on both ports 1 and 2. Administered IHS **706** may access adapter **715** to communicate via NETWORK A **713**.

The hardware configuration information of adapter **719** includes MSN of 003F230A, PID of 0111, LID of 0DA1, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **719** is located in physical channel 0111 in administered IHS **708** and may be identified logically by administered IHS **708** as 0DA1. Adapter **719** is a physical OSA network adapter and couples to NETWORK B **718** on both ports 1 and 2. Administered IHS **708** may access adapter **719** to communicate via NETWORK B **718**.

The hardware configuration information of adapter **720** includes MSN of 003F230A, PID of 0112, LID of 0DA2, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **720** is located in physical channel 0112 in administered IHS **708** and may be identified logically by administered IHS **708** as 0DA2. Adapter **720** is a physical RNIC network adapter and couples to NETWORK B **718** on both ports 1 and 2. Administered IHS **708** may access adapter **720** to communicate via NETWORK B **718**.

The hardware configuration information of adapter **724** includes MSN of 003F230A, PID of 020E, LID of 0024, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **724** is located in physical channel 020E in administered IHS **708** and may be identified logically by administered IHS **708** as 0024. Adapter **724** is a physical OSA network adapter and couples to NETWORK C **723** on both ports 1 and 2. Administered IHS **708** may access adapter **724** to communicate via NETWORK C **723**.

The hardware configuration information of adapter **725** includes MSN of 003F230A, PID of 020F, LID of 0025, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **725** is located in physical channel 020F in administered IHS **708** and may be identified logically by administered IHS **708** as 0025. Adapter **725** is a physical RNIC network adapter and couples to NETWORK C **723** on both ports 1 and 2. Administered IHS **708** may access adapter **725** to communicate via NETWORK C **723**.

The hardware configuration information of adapter **726** includes MSN of 668A2B01, PID of 0117, LID of 06D0, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **726** is located in physical channel 0117 in administered IHS **710** and may be identified logically by administered IHS **710** as 06D0. Adapter **726** is a physical OSA network adapter and couples to NETWORK C **723** on both ports 1 and 2. Administered IHS **710** may access adapter **726** to communicate via NETWORK C **723**.

As illustrated in FIG. 7, RNIC converging tool **1200** may group OSA adapter **711** with RNIC adapter **712**. RNIC converging tool **1200** may sort the adapters by PNet IDs and by type to group OSA and RNIC type adapters together. RNIC converging tool **1200** may group OSA adapter **711** with RNIC adapter **712**, allowing the adapters to function together on NETWORK A **713**. These grouped adapters, i.e. RNIC con-

22

verged adapters, allow LPARs to easily utilize the adapters for RDMA communications. RDMA is remote direct memory access, a technology that enables an IHS to exchange information with another IHS without involving the processor, cache or operating system.

FIG. 9 is a block diagram showing one embodiment of the disclosed remote RNIC converging system **900** utilizing PNet IDs. RNIC converging system **900** may utilize network adapter **901**, administrative network **902** and network adapter **903** to couple HCM IHS **500** to administered IHS **904**. Administered IHS **904** may also be referred to as RNIC converging IHS **904**. RNIC converging system **900** may utilize network adapter **901**, administrative network **902** and network adapter **905** to couple HCM IHS **500** to administered IHS **906**. RNIC converging system **900** may utilize network adapter **901**, administrative network **902** and network adapter **907** to couple HCM IHS **500** to administered IHS **908**. Administered IHSs **904**, **906** and **908** couple via administrative network **902** to HCM IHS **500** to enable HCM IHS **500** to administer HCM database **1000** with HCM tool **600** to the administered IHSs.

RNIC converging system **900** may utilize network adapter **909** and/or network adapter **910** and/or network adapter **912** and/or network adapter **913** and/or network adapter **914** and/or network adapter **915** and/or network adapter **916** and/or network adapter **917** and/or network adapter **918** and/or network adapter **919** via NETWORK A **920** via network adapter **921** and/or network adapter **922** and/or network adapter **923** and/or network adapter **924** to couple RNIC converging IHS **904** to administered IHS **906**. RNIC converging system **900** may utilize network adapter **925** and/or network adapter **926** and/or network adapter **927** and/or network adapter **928** and/or network adapter **929** and/or network adapter **930** and/or network adapter **931** and/or network adapter **932** and/or network adapter **933** and/or network adapter **934** via NETWORK B **935** via network adapter **936** and/or network adapter **937** and/or network adapter **938** and/or network adapter **939** to couple RNIC converging IHS **904** to administered IHS **908**.

In one embodiment, network adapter **901**, **903**, **905** and **907** may be Ethernet (ETH) adapters. Network adapters **909**, **911**, **913**, **915**, **917**, **918**, **919**, **921**, **923**, **925**, **927** and **929** may be open system adapters (OSAs). Network adapters **910**, **912**, **914**, **916**, **922**, **924**, **926**, **928**, **930**, **931**, **932**, **933** and **934** may be remote direct memory access (RDMA) enabled network adapter controllers (RNICs). In one embodiment, administrative network **902**, NETWORK A **920** and NETWORK B **935** may provide local area network (LAN) communications and/or wide area network (WAN) communications and/or virtual LAN communications and/or intranet communications and/or Internet communications to structures that couple thereto.

RNIC converging IHS **904** may include a hypervisor (not shown) that may create logical partition (LPAR) **940-1**, LPAR **940-2**, LPAR **940-3**, LPAR **940-4**, LPAR **940-5**, LPAR **940-6**, LPAR **940-7**, LPAR **940-8**, LPAR **940-9**, LPAR **940-10** and LPAR **940-11** in RNIC converging IHS **904**. LPAR **940-1**, LPAR **940-2**, LPAR **940-3**, LPAR **940-4**, LPAR **940-5**, LPAR **940-6**, LPAR **940-7**, LPAR **940-8**, LPAR **940-9**, LPAR **940-10** and LPAR **940-11** may include virtual network adapters. In one embodiment, the virtual network adapters may be ETH, OSA or RNIC type virtual network adapters.

Referring to the HCM database **1000** of FIG. 10 in conjunction with the RNIC converging system **900** of FIG. 9, LPAR **940-1**, LPAR **940-2**, LPAR **940-3**, LPAR **940-4**, LPAR **940-8**, LPAR **940-9**, LPAR **940-10** and LPAR **940-11** may each include a respective OSA type virtual network adapter. The OSA type virtual network adapters of LPAR **940-1**,

23

LPAR 940-2, 940-3, 940-4, LPAR 940-8, LPAR 940-9, LPAR 940-10 and LPAR 940-11 may couple to network adapter 909 via a channel, i.e., a bus. LPAR 940-1, LPAR 940-2, LPAR 940-3, LPAR 940-4, LPAR 940-8, LPAR 940-9, LPAR 940-10 and LPAR 940-11 may each include a respective RNIC type virtual network adapter. The RNIC type virtual network adapters of LPAR 940-1, LPAR 940-2, 940-3, 940-4, LPAR 940-8, LPAR 940-9, LPAR 940-10 and LPAR 940-11 may couple to network adapter 910 via a channel.

LPAR 940-4, LPAR 940-5, LPAR 940-6 and LPAR 940-7 may each include a respective OSA type virtual network adapter. The OSA type virtual network adapters of LPAR 940-4, LPAR 940-5, 940-6 and LPAR 940-7 may couple to network adapter 911 via a channel. LPAR 940-4, LPAR 940-5, LPAR 940-6 and LPAR 940-7 may each include a respective RNIC type virtual network adapter. The RNIC type virtual network adapters of LPAR 940-4, LPAR 940-5, 940-6 and LPAR 940-7 may couple to network adapter 912 via a channel.

LPAR 940-3 may include an OSA type virtual network adapter. The OSA type virtual network adapter of LPAR 940-3 may couple to network adapter 913 via a channel. LPAR 940-3 may include an RNIC type virtual network adapter. The RNIC type virtual network adapters of LPAR 940-3 may couple to network adapter 914 via a channel.

LPAR 940-2, LPAR 940-4, LPAR 940-6, LPAR 940-8 and LPAR 940-10 may each include a respective OSA type virtual network adapter. The OSA type virtual network adapters of LPAR 940-2, LPAR 940-4, 940-6, LPAR 940-8 and LPAR 940-10 may couple to network adapter 915 via a channel. LPAR 940-2, LPAR 940-4, LPAR 940-6, LPAR 940-8 and LPAR 940-10 may each include a respective RNIC type virtual network adapter. The RNIC type virtual network adapters of LPAR 940-2, LPAR 940-4, 940-6, LPAR 940-8 and LPAR 940-10 may couple to network adapter 916 via a channel.

LPAR 940-1, LPAR 940-2, LPAR 940-3, LPAR 940-4, LPAR 940-5, LPAR 940-6, LPAR 940-7 and LPAR 940-8 may each include a respective OSA type virtual network adapter. The OSA type virtual network adapters of LPAR 940-1, LPAR 940-2, 940-3, 940-4, LPAR 940-5, LPAR 940-6, LPAR 940-7 and LPAR 940-8 may couple to network adapter 917 via a channel. LPAR 940-1, LPAR 940-2, LPAR 940-3, LPAR 940-4, LPAR 940-7, LPAR 940-9, LPAR 940-10 and LPAR 940-11 may each include a respective OSA type virtual network adapter. The OSA type virtual network adapters of LPAR 940-1, LPAR 940-2, 940-3, 940-4, LPAR 940-7, LPAR 940-9, LPAR 940-10 and LPAR 940-11 may couple to network adapter 918 via a channel. LPAR 940-1, LPAR 940-3, LPAR 940-5, LPAR 940-7, LPAR 940-8, LPAR 940-9, LPAR 940-10 and LPAR 940-11 may each include a respective OSA type virtual network adapter. The OSA type virtual network adapters of LPAR 940-1, LPAR 940-3, 940-5, 940-7, LPAR 940-8, LPAR 940-9, LPAR 940-10 and LPAR 940-11 may couple to network adapter 919 via a channel.

LPAR 940-1, LPAR 940-2, LPAR 940-3, LPAR 940-4, LPAR 940-5, LPAR 940-6, LPAR 940-7 and LPAR 940-8 may each include a respective OSA type virtual network adapter. The OSA type virtual network adapters of LPAR 940-1, LPAR 940-2, 940-3, 940-4, LPAR 940-5, LPAR 940-6, LPAR 940-7 and LPAR 940-8 may couple to network adapter 925 via a channel. LPAR 940-1, LPAR 940-2, LPAR 940-3, LPAR 940-4, LPAR 940-5, LPAR 940-6, LPAR 940-7 and LPAR 940-8 may each include a respective RNIC type virtual network adapter. The RNIC type virtual network adapters of LPAR 940-1, LPAR 940-2, 940-3, 940-4, LPAR 940-5, LPAR 940-6, LPAR 940-7 and LPAR 940-8 may couple to network adapter 926 via a channel.

24

LPAR 940-9, LPAR 940-10 and LPAR 940-11 may each include a respective OSA type virtual network adapter. The OSA type virtual network adapters of LPAR 940-9, LPAR 940-10 and LPAR 940-11 may couple to network adapter 927 via a channel. LPAR 940-9, LPAR 940-10 and LPAR 940-11 may each include a respective RNIC type virtual network adapter. The RNIC type virtual network adapters of LPAR 940-9, LPAR 940-10 and LPAR 940-11 may couple to network adapter 928 via a channel.

LPAR 940-1, LPAR 940-3, LPAR 940-5 and LPAR 940-7 may each include a respective OSA type virtual network adapter. The OSA type virtual network adapters of LPAR 940-1, LPAR 940-3, LPAR 940-5 and LPAR 940-7 may couple to network adapter 929 via a channel. LPAR 940-1, LPAR 940-3, LPAR 940-5 and LPAR 940-7 may each include a respective RNIC type virtual network adapter. The RNIC type virtual network adapters of LPAR 940-1, LPAR 940-3, LPAR 940-5 and LPAR 940-7 may couple to network adapter 930 via a channel.

LPAR 940-1, LPAR 940-2, LPAR 940-3, LPAR 940-4, LPAR 940-5, LPAR 940-6, LPAR 940-7 and LPAR 940-8 may each include a respective RNIC type virtual network adapter. The RNIC type virtual network adapters of LPAR 940-1, LPAR 940-2, 940-3, 940-4, LPAR 940-5, LPAR 940-6, LPAR 940-7 and LPAR 940-8 may couple to network adapter 931 via a channel. LPAR 940-1, LPAR 940-2, LPAR 940-3, LPAR 940-4, LPAR 940-7, LPAR 940-9, LPAR 940-10 and LPAR 940-11 may each include a respective RNIC type virtual network adapter. The RNIC type virtual network adapters of LPAR 940-1, LPAR 940-2, 940-3, 940-4, LPAR 940-7, LPAR 940-9, LPAR 940-10 and LPAR 940-11 may couple to network adapter 932 via a channel.

LPAR 940-1, LPAR 940-2, LPAR 940-3, LPAR 940-4, LPAR 940-5, LPAR 940-6, LPAR 940-7 and LPAR 940-8 may each include a respective RNIC type virtual network adapter. The RNIC type virtual network adapters of LPAR 940-1, LPAR 940-2, 940-3, 940-4, LPAR 940-5, LPAR 940-6, LPAR 940-7 and LPAR 940-8 may couple to network adapter 933 via a channel. LPAR 940-1, LPAR 940-2, LPAR 940-3, LPAR 940-4, LPAR 940-7, LPAR 940-9, LPAR 940-10 and LPAR 940-11 may each include a respective RNIC type virtual network adapter. The RNIC type virtual network adapters of LPAR 940-1, LPAR 940-2, 940-3, 940-4, LPAR 940-7, LPAR 940-9, LPAR 940-10 and LPAR 940-11 may couple to network adapter 934 via a channel.

FIG. 10 depicts one embodiment of HCM database 1000 in the disclosed RNIC converging system 900. HCM tool 600 may store the hardware configuration information in HCM database 1000 on a per adapter basis. In one embodiment, for each network adapter in RNIC converging system 900, HCM tool 600 may store, from the leftmost column to the rightmost column, the machine serial number (MSN), physical identification (PID), logical identification (LID), adapter type, logical partition (LPAR) access list, physical network identification (PNet ID) for a first port of the network adapter, and the PNet ID for the second port of the network adapter.

As shown in HCM database 1000, the hardware configuration information of adapter 909 includes MSN of 000F3801, PID of 0011, LID of 00F0, type of 0087, LPAR access list of 01, 02, 03, 04, 08, 09, 0A and 0B, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter 909 is located in physical channel 0011 in RNIC converging IHS 904 and may be identified logically by RNIC converging IHS 904 as 00F0. Adapter 909 is a physical OSA network adapter and couples to NETWORK A 920 on both ports 1 and 2. LPAR 940-1, 940-2, 940-3, 940-4, 940-8, 940-9, 940-10 and

25

940-11 of RNIC converging IHS **904** may access adapter **909** to communicate via NETWORK A **920**.

The hardware configuration information of adapter **910** includes MSN of 000F3801, PID of 0020, LID of 05C0, type of 0008, LPAR access list of 01, 02, 03, 04, 08, 09, 0A and 0B, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **910** is located in physical channel 0020 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 05C0. Adapter **910** is a physical RNIC network adapter and couples to NETWORK A **920** on both ports 1 and 2. LPAR **940-1**, **940-2**, **940-3**, **940-4**, **940-8**, **940-9**, **940-10** and **940-11** of RNIC converging IHS **904** may access adapter **910** to communicate via NETWORK A **920**.

The hardware configuration information of adapter **911** includes MSN of 000F3801, PID of 0012, LID of 00F9, type of 0087, LPAR access list of 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **911** is located in physical channel 0012 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 00F9. Adapter **911** is a physical OSA network adapter and couples to NETWORK A **920** on both ports 1 and 2. LPAR **940-4**, **940-5**, **940-6** and **940-7** of RNIC converging IHS **904** may access adapter **911** to communicate via NETWORK A **920**.

The hardware configuration information of adapter **912** includes MSN of 000F3801, PID of 0021, LID of 05C9, type of 0008, LPAR access list of 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **912** is located in physical channel 0021 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 05C9. Adapter **912** is a physical RNIC network adapter and couples to NETWORK A **920** on both ports 1 and 2. LPAR **940-4**, **940-5**, **940-6** and **940-7** of RNIC converging IHS **904** may access adapter **912** to communicate via NETWORK A **920**.

The hardware configuration information of adapter **913** includes MSN of 000F3801, PID of 0013, LID of 00FE, type of 0087, LPAR access list of 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **913** is located in physical channel 0013 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 00FE. Adapter **913** is a physical OSA network adapter and couples to NETWORK A **920** on both ports 1 and 2. LPAR **940-3** of RNIC converging IHS **904** may access adapter **913** to communicate via NETWORK A **920**.

The hardware configuration information of adapter **914** includes MSN of 000F3801, PID of 0022, LID of 05CE, type of 0008, LPAR access list of 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **914** is located in physical channel 0022 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 05CE. Adapter **914** is a physical RNIC network adapter and couples to NETWORK A **920** on both ports 1 and 2. LPAR **940-3** of RNIC converging IHS **904** may access adapter **914** to communicate via NETWORK A **920**.

The hardware configuration information of adapter **915** includes MSN of 000F3801, PID of 0014, LID of 0100, type of 0087, LPAR access list of 02, 04, 06, 08 and 0A, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **915** is located in physical channel 0014 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 0100. Adapter **915** is a physical OSA network adapter and couples to NETWORK A **920** on both ports 1 and 2. LPAR **940-2**, **940-4**, **940-6**, **940-8** and **940-10** of RNIC converging IHS **904** may access adapter **915** to communicate via NETWORK A **920**.

26

The hardware configuration information of adapter **916** includes MSN of 000F3801, PID of 0023, LID of 0600, type of 0008, LPAR access list of 02, 04, 06, 08 and 0A, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **916** is located in physical channel 0023 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 0600. Adapter **916** is a physical RNIC network adapter and couples to NETWORK A **920** on both ports 1 and 2. LPAR **940-2**, **940-4**, **940-6**, **940-8** and **940-10** of RNIC converging IHS **904** may access adapter **916** to communicate via NETWORK A **920**.

The hardware configuration information of adapter **917** includes MSN of 000F3801, PID of 0015, LID of 0106, type of 0087, LPAR access list of 01, 02, 03, 04, 05, 06, 07 and 08, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **917** is located in physical channel 0015 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 0106. Adapter **917** is a physical OSA network adapter and couples to NETWORK A **920** on both ports 1 and 2. LPAR **940-1**, **940-2**, **940-3**, **940-4**, **940-5**, **940-6**, **940-7** and **940-8** of RNIC converging IHS **904** may access adapter **917** to communicate via NETWORK A **920**.

The hardware configuration information of adapter **918** includes MSN of 000F3801, PID of 0016, LID of 010F, type of 0087, LPAR access list of 01, 02, 03, 04, 07, 09, 0A and 0B, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **918** is located in physical channel 0016 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 010F. Adapter **918** is a physical OSA network adapter and couples to NETWORK A **920** on both ports 1 and 2. LPAR **940-1**, **940-2**, **940-3**, **940-4**, **940-7**, **940-9**, **940-10** and **940-11** of RNIC converging IHS **904** may access adapter **918** to communicate via NETWORK A **920**.

The hardware configuration information of adapter **919** includes MSN of 000F3801, PID of 0017, LID of 0118, type of 0087, LPAR access list of 01, 03, 05, 07, 08, 09, 0A and 0B, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **919** is located in physical channel 0017 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 0118. Adapter **919** is a physical OSA network adapter and couples to NETWORK A **920** on both ports 1 and 2. LPAR **940-1**, **940-3**, **940-5**, **940-7**, **940-8**, **940-9**, **940-10** and **940-11** of RNIC converging IHS **904** may access adapter **919** to communicate via NETWORK A **920**.

The hardware configuration information of adapter **925** includes MSN of 000F3801, PID of 0018, LID of 0120, type of 0087, LPAR access list of 01, 02, 03, 04, 05, 06, 07 and 08, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **925** is located in physical channel 0018 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 0120. Adapter **925** is a physical OSA network adapter and couples to NETWORK B **935** on both ports 1 and 2. LPAR **940-1**, **940-2**, **940-3**, **940-4**, **940-5**, **940-6**, **940-7** and **940-8** of RNIC converging IHS **904** may access adapter **925** to communicate via NETWORK B **935**.

The hardware configuration information of adapter **926** includes MSN of 000F3801, PID of 0024, LID of 0606, type of 0008, LPAR access list of 01, 02, 03, 04, 05, 06, 07 and 08, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **926** is located in physical channel 0024 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 0606. Adapter **926** is a physical RNIC network adapter and couples to NETWORK B **935** on both ports 1 and 2. LPAR **940-1**, **940-2**, **940-3**, **940-4**, **940-5**, **940-6**, **940-7** and **940-8** of RNIC converging IHS **904** may access adapter **926** to communicate via NETWORK B **935**.

The hardware configuration information of adapter **927** includes MSN of 000F3801, PID of 0019, LID of 0129, type of 0087, LPAR access list of 09, 0A and 0B, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **927** is located in physical channel 0019 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 0129. Adapter **927** is a physical OSA network adapter and couples to NETWORK B **935** on both ports 1 and 2. LPAR **940-9**, **940-10** and **940-11** of RNIC converging IHS **904** may access adapter **927** to communicate via NETWORK B **935**.

The hardware configuration information of adapter **928** includes MSN of 000F3801, PID of 0025, LID of 060F, type of 0008, LPAR access list of 09, 0A and 0B, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **928** is located in physical channel 0025 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 060F. Adapter **928** is a physical RNIC network adapter and couples to NETWORK B **935** on both ports 1 and 2. LPAR **940-9**, **940-10** and **940-11** of RNIC converging IHS **904** may access adapter **928** to communicate via NETWORK B **935**.

The hardware configuration information of adapter **929** includes MSN of 000F3801, PID of 001A, LID of 012D, type of 0087, LPAR access list of 01, 03, 05 and 07, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **929** is located in physical channel 001A in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 012D. Adapter **929** is a physical OSA network adapter and couples to NETWORK B **935** on both ports 1 and 2. LPAR **940-1**, **940-3**, **940-5** and **940-7** of RNIC converging IHS **904** may access adapter **929** to communicate via NETWORK B **935**.

The hardware configuration information of adapter **930** includes MSN of 000F3801, PID of 0026, LID of 0613, type of 0008, LPAR access list of 01, 03, 05 and 07, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **930** is located in physical channel 0026 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 0613. Adapter **930** is a physical RNIC network adapter and couples to NETWORK B **935** on both ports 1 and 2. LPAR **940-1**, **940-3**, **940-5** and **940-7** of RNIC converging IHS **904** may access adapter **930** to communicate via NETWORK B **935**.

The hardware configuration information of adapter **931** includes MSN of 000F3801, PID of 0027, LID of 0618, type of 0008, LPAR access list of 01, 02, 03, 04, 05, 06, 07 and 08, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **931** is located in physical channel 0027 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 0618. Adapter **931** is a physical RNIC network adapter and couples to NETWORK B **935** on both ports 1 and 2. LPAR **940-1**, **940-2**, **940-3**, **940-4**, **940-5**, **940-6**, **940-7** and **940-8** of RNIC converging IHS **904** may access adapter **931** to communicate via NETWORK B **935**.

The hardware configuration information of adapter **932** includes MSN of 000F3801, PID of 0028, LID of 0621, type of 0008, LPAR access list of 01, 02, 03, 04, 07, 09, 0A and 0B, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **932** is located in physical channel 0028 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 0621. Adapter **932** is a physical RNIC network adapter and couples to NETWORK B **935** on both ports 1 and 2. LPAR **940-1**, **940-2**, **940-3**, **940-4**, **940-7**, **940-9**, **940-10** and **940-11** of RNIC converging IHS **904** may access adapter **932** to communicate via NETWORK B **935**.

The hardware configuration information of adapter **933** includes MSN of 000F3801, PID of 0029, LID of 062A, type of 0008, LPAR access list of 01, 02, 03, 04, 05, 06, 07 and 08, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **933** is located in physical channel 0029 in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 062A. Adapter **933** is a physical RNIC network adapter and couples to NETWORK B **935** on both ports 1 and 2. LPAR **940-1**, **940-2**, **940-3**, **940-4**, **940-5**, **940-6**, **940-7** and **940-8** of RNIC converging IHS **904** may access adapter **933** to communicate via NETWORK B **935**.

The hardware configuration information of adapter **934** includes MSN of 000F3801, PID of 002A, LID of 0633, type of 0008, LPAR access list of 01, 02, 03, 04, 07, 09, 0A and 0B, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **934** is located in physical channel 002A in RNIC converging IHS **904** and may be identified logically by RNIC converging IHS **904** as 0633. Adapter **934** is a physical RNIC network adapter and couples to NETWORK B **935** on both ports 1 and 2. LPAR **940-1**, **940-2**, **940-3**, **940-4**, **940-7**, **940-9**, **940-10** and **940-11** of RNIC converging IHS **904** may access adapter **934** to communicate via NETWORK B **935**.

The hardware configuration information of adapter **921** includes MSN of 03006FF7, PID of 0101, LID of 0F01, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **921** is located in physical channel 0101 in administered IHS **906** and may be identified logically by administered IHS **906** as 0F01. Adapter **921** is a physical OSA network adapter and couples to NETWORK A **920** on both ports 1 and 2. Administered IHS **906** may access adapter **921** to communicate via NETWORK A **920**.

The hardware configuration information of adapter **922** includes MSN of 03006FF7, PID of 0201, LID of 0F02, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **922** is located in physical channel 0201 in administered IHS **906** and may be identified logically by administered IHS **906** as 0F02. Adapter **922** is a physical RNIC network adapter and couples to NETWORK A **920** on both ports 1 and 2. Administered IHS **906** may access adapter **922** to communicate via NETWORK A **920**.

The hardware configuration information of adapter **923** includes MSN of 03006FF7, PID of 0102, LID of 0F03, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **923** is located in physical channel 0102 in administered IHS **906** and may be identified logically by administered IHS **906** as 0F03. Adapter **923** is a physical OSA network adapter and couples to NETWORK A **920** on both ports 1 and 2. Administered IHS **906** may access adapter **923** to communicate via NETWORK A **920**.

The hardware configuration information of adapter **924** includes MSN of 03006FF7, PID of 0202, LID of 0F04, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **924** is located in physical channel 0202 in administered IHS **906** and may be identified logically by administered IHS **906** as 0F04. Adapter **924** is a physical RNIC network adapter and couples to NETWORK A **920** on both ports 1 and 2. Administered IHS **906** may access adapter **924** to communicate via NETWORK A **920**.

The hardware configuration information of adapter **936** includes MSN of D832900A, PID of 0055, LID of DD06, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **936** is located in physical channel 0055 in administered IHS **908** and

may be identified logically by administered IHS **908** as DD06. Adapter **936** is a physical OSA network adapter and couples to NETWORK B **935** on both ports 1 and 2. Administered IHS **908** may access adapter **936** to communicate via NETWORK B **935**.

The hardware configuration information of adapter **937** includes MSN of D832900A, PID of 0057, LID of DD07, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **937** is located in physical channel 0057 in administered IHS **908** and may be identified logically by administered IHS **908** as DD07. Adapter **937** is a physical RNIC network adapter and couples to NETWORK B **935** on both ports 1 and 2. Administered IHS **908** may access adapter **937** to communicate via NETWORK B **935**.

The hardware configuration information of adapter **938** includes MSN of D832900A, PID of 0056, LID of DD08, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **938** is located in physical channel 0056 in administered IHS **908** and may be identified logically by administered IHS **908** as DD08. Adapter **938** is a physical OSA network adapter and couples to NETWORK B **935** on both ports 1 and 2. Administered IHS **908** may access adapter **938** to communicate via NETWORK B **935**.

The hardware configuration information of adapter **939** includes MSN of D832900A, PID of 0058, LID of DD09, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **939** is located in physical channel 0058 in administered IHS **908** and may be identified logically by administered IHS **908** as DD09. Adapter **939** is a physical RNIC network adapter and couples to NETWORK B **935** on both ports 1 and 2. Administered IHS **908** may access adapter **939** to communicate via NETWORK B **935**.

As illustrated in FIG. 9, RNIC converging tool **1200** may group many OSA adapters with RNIC adapters, thus creating RNIC converged adapters. To create RNIC converged adapters, RNIC converging tool **1200** may sort the adapters by PNet IDs and adapter types. In one embodiment, RNIC converged adapters should be on the same network to function. Without PNet IDs and adapter types, RNIC converging tool **1200** would not be able to create RNIC converged adapters on the same network.

RNIC converged adapters allow OSA adapter **909** to initiate TCP/IP communications. When converged with RNIC adapter **910**, RDMA communications may be more readily initiated and conducted. RNIC converged adapters allow LPARs to easily utilize the RNIC converging adapters for RDMA communications. RDMA communications may exhibit lower latency than TCP/IP communications. RDMA is remote direct memory access, a technology that enables an IHS to exchange information with another IHS without involving the processor, cache or operating system.

With respect to an RNIC converging IHS, the disclosed methodology logically causes two unlike adapters, such as OSA and RNIC adapters, that are connected to or associated with the same physical network to function together, i.e. to converge, as if the two adapters were a single adapter (i.e. using standard TCP/IP protocol over the OSA and RDMA protocols over the RNIC).

FIG. 11 is a block diagram of an RNIC converging information handling system (IHS) **1100** that may be used in the disclosed RNIC converging system. RNIC converging IHS **1100** includes a processor **1105** that may include multiple cores. RNIC converging IHS **1100** processes, transfers, communicates, modifies, stores or otherwise handles information

in digital form, analog form or other form. In one embodiment, RNIC converging IHS **1100** includes a bus **1110**, i.e. channel **1110**. In another embodiment, bus **1110** may be multiple busses, i.e., multiple channels. Bus **1110** may couple processor **1105** to memory **1115** via a memory controller **1120** and memory bus **1125**. System memory **1115** may also be referred to as main memory. System memory **1115** may be a static random access memory (SRAM) array or a dynamic random access memory (DRAM) array. Processor **1105** may also include local memory such as L1, L2 and L3 caches.

In one embodiment, a video graphics controller **1130** couples display **1135** to bus **1110**. In another embodiment, RNIC converging IHS **1100** may operate without display **1135** and/or video graphics controller **1130**. Nonvolatile storage **1140**, such as a hard disk drive, solid-state drive (SSD), CD drive, DVD drive, or other nonvolatile storage couples to bus **1110** to provide RNIC converging IHS **1100** with permanent storage of information. System memory **1115** and nonvolatile storage **1140** are both forms of memory stores. In one embodiment, nonvolatile storage **1140** stores a hypervisor **1145** (HYPERVISOR) that governs operation of RNIC converging IHS **1100**. In another embodiment, nonvolatile storage **1140** may store an operating system (not shown) that governs operation of RNIC converging IHS **1100**. In another embodiment, nonvolatile storage **1140** may store an operating system (not shown) that governs operation of RNIC converging IHS **1100**, where the operating system includes a hypervisor (not shown).

I/O devices **1150**, such as speakers, a keyboard and a pointing device, may couple to bus **1110** via I/O controller **1155** and I/O bus **1160**. One or more expansion busses **1165**, i.e. channels **1165**, such as USB, IEEE 1394 bus, ATA, SATA, PCI, PCIE, DVI, HDMI and other busses, i.e. channels, couple to bus **1110** to facilitate the connection of peripherals and devices to RNIC converging IHS **1100**. Network interface controllers (NICs), for example, NIC **1170-1**, NIC **1170-2**, . . . , NIC **1170-N**, wherein N is the number of NICs, may couple to bus **1110** to enable RNIC converging IHS **1100** to connect by wire or wirelessly to a network and other information handling systems. NIC **1170-1**, NIC **1170-2**, . . . , NIC **1170-N** may also be called a network communication adapter, network interface adapter, network adapter, network interface and/or an adapter. NIC **1170-1**, NIC **1170-2**, . . . , NIC **1170-N** may take many forms. For example, NIC **1170-1**, NIC **1170-2**, . . . , NIC **1170-N** may take the form of an Ethernet (ETH) adapter, open systems adapter (OSA), RDMA enabled network interface controller (RN IC) or other network communication adapter.

While FIG. 11 shows one IHS that employs processor **1105**, the IHS may take many forms. For example, RNIC converging IHS **1100** may take the form of a mainframe, server, central processor complex (CPC), desktop, portable, laptop, notebook, tablet or other form factor computer or data processing system. RNIC converging IHS **1100** may take other form factors such as a gaming device, a personal digital assistant (PDA), a portable telephone device, a communication device or other devices that include a processor and memory.

RNIC converging IHS **1100** includes a RNIC converging tool computer program product **1200** on digital media **1175** such as a CD, DVD or other media. For simplicity, the term RNIC converging tool will be used below. RNIC converging IHS **1100** may store RNIC converging tool **1200** in nonvolatile storage **1140** as RNIC converging tool **1200**. RNIC converging IHS **1100** may also store hypervisor **1145** (HYPERVISOR) and logical partition (LPAR) **1180-1**, LPAR

31

1180-2, . . . , LPAR 1180-M, wherein M is the number of LPARs, in nonvolatile storage 1140.

In another embodiment, RNIC converging tool 1200' may be part of the hypervisor 1145 (not shown). In another embodiment, RNIC converging tool 1200' may be in LPAR 1180-1, LPAR 1180-2, . . . , LPAR 1180-M. In another embodiment, RNIC converging IHS 1100 may store an operating system (not shown) that governs operation of RNIC converging IHS 1100, where the operating system includes a hypervisor (not shown) and where the operating system includes LPAR 1180-1, LPAR 1180-2, . . . , LPAR 1180-M as virtual machines (not shown). When RNIC converging IHS 1100 initializes, the IHS loads hypervisor 1145 into system memory 1115 for execution as hypervisor 1145'. RNIC converging IHS 1100 also loads RNIC converging tool 1200' into system memory 1115 for execution as RNIC converging tool 1200". RNIC converging IHS 1100 may also load LPAR 1180-1, LPAR 1180-2, . . . , LPAR 1180-M into system memory 1115 for execution as LPAR 1180-1', LPAR 1180-2', . . . , LPAR 1180-M', respectively.

In another embodiment, when RNIC converging IHS 1100 initializes, the IHS may load an operating system (not shown) into system memory 1115 for execution. In another embodiment, when RNIC converging IHS 1100 initializes, the IHS may load an operating system (not shown) that includes a hypervisor (not shown) and includes LPAR 1180-1, LPAR 1180-2, . . . , LPAR 1180-M as virtual machines (not shown) into system memory 1115 for execution.

FIG. 12 is a flowchart that shows a representative process flow of an RNIC converging tool 1200 that may be used in the disclosed RNIC converging system. Process flow commences when RNIC converging tool 1200 in RNIC converging IHS 1100 initializes, as per block 1205. If HCM tool 600 in HCM IHS 500 does not transmit HCM database 580, as per block 1210, process flow continues at block 1210. If HCM tool 600 in HCM IHS 500 does transmit HCM database 580, as per block 1210, a hypervisor agent in RNIC converging IHS 1100 may receive HCM database 580, as per block 1215. In one embodiment, the hypervisor agent in the RNIC converging IHS 1100 is included in hypervisor 1145.

The hypervisor agent may allow hypervisor 1145 to access HCM database 580. Hypervisor 1145 may transmit HCM database 580 to RNIC converging tool 1200, as per block 1220. RNIC converging tool 1200 may extract the hardware configuration information of RNIC converging IHS 1100 from the HCM database 580, as per block 1225. In one embodiment, the hardware configuration information of RNIC converging IHS 1100 from HCM database 580 may include, but is not limited to, on a per adapter basis, machine serial numbers (MSNs), physical identifications (PIDs), logical identifications (LIDs), adapter type, logical partition (LPAR) access list, physical network identification (PNet ID) of the first port of the adapter and the PNet ID of the second port of the adapter. In one embodiment, the adapter type "0087" may be an OSA adapter and the adapter type "0008" may be an RNIC adapter.

In one embodiment, the RNIC converging tool 1200 may share the extracted hardware configuration information of RNIC converging IHS 1100 with hypervisor 1145. Hypervisor 1145 may update the hardware configuration of RNIC converging IHS 1100 with the extracted hardware configuration information of RNIC converging IHS 1100. In another embodiment, the RNIC converging tool 1200 may share the extracted hardware configuration information of RNIC converging IHS 1100 with LPARs 1180-1, 1180-2, . . . , 1180-M, where M is the number of LPARs in RNIC converging IHS 1100. LPARs 1180-1, 1180-2, . . . , 1180-M may update their

32

respective hardware configuration with the extracted hardware configuration information of RNIC converging IHS 1100.

RNIC converging tool 1200 may sort the extracted hardware configuration information by PNet IDs, as per block 1230. For example, the RNIC converging tool 1200 may list all adapters with the PNet ID of "NETA" first, followed by all adapters with the PNet ID of "NETB". RNIC converging tool 1200 may further sort the extracted configuration information by adapter type, as per block 1235. For example, the RNIC converging tool 1200 may list all adapters with the type "0087" and the PNet ID "NETA" first, followed by the adapters with the type "0008" and the PNet ID of "NETA", further followed by the adapters with the type "0087" and the PNet ID of "NETB".

In one embodiment, RNIC converging tool 1200 may group OSA adapters and RNIC adapters with matching PNet IDs, as per block 1240. For example, as shown in FIGS. 7 and 8, RNIC converging tool 1200 may group network adapter 711 and network adapter 712 together because adapter 711 is the type "0087", i.e. OSA, and adapter 712 is the type "0008", i.e. RNIC, and both adapters 711 and 712 have a PNet ID of "NETA". The RNIC converging tool 1200 may allow an LPAR with access to utilize the grouped adapters to communicate using RDMA, which may require both an OSA and RNIC adapter, as per block 1245. Process flow terminates at end block 1250. Alternatively, process flow may continue at start block 605.

III. Bridging System

FIG. 13 is a block diagram showing one embodiment of the disclosed bridging system 1300 utilizing PNet IDs. Bridging system 1300 may utilize network adapter 1301, administrative network 1302 and network adapter 1303 to couple HCM IHS 500 to administered IHS 1304. Administered IHS 1304 may be referred to as bridging IHS 1304. Bridging system 1300 may utilize network adapter 1301, administrative network 1302 and network adapter 1305 to couple HCM IHS 500 to administered IHS 1306. Bridging system 1300 may utilize network adapter 1301, administrative network 1302 and network adapter 1307 to couple HCM IHS 500 to administered IHS 1308. Bridging system 1300 may utilize network adapter 1301, administrative network 1302 and network adapter 1309 to couple HCM IHS 500 to administered IHS 1310. Administered IHSs 1304, 1306, 1308 and 1310 couple via administrative network 1302 to HCM IHS 500 to enable HCM IHS 500 to administer HCM database 1400 with HCM tool 600 to the administered IHSs.

Bridging system 1300 may utilize network adapter 1311 via NETWORK A 1312 via network adapter 1313 to couple bridging IHS 1304 to administered IHS 1306. Bridging system 1300 may utilize network adapter 1314 via NETWORK B 1315 via network adapter 1316 to couple bridging IHS 1304 to administered IHS 1308. Bridging system 1300 may utilize network adapter 1317 via NETWORK C 1318 via network adapter 1319 to couple bridging IHS 1304 to administered IHS 1310.

In one embodiment, network adapters 1301, 1303, 1305, 1307 and 1309 may be Ethernet (ETH) adapters. Network adapters 1311, 1313, 1314, 1316, 1317 and 1319 may be open system adapters (OSAs). In one embodiment, administrative network 1302, NETWORK A 1312, NETWORK B 1315 and NETWORK C 1318 may provide local area network (LAN) communications and/or wide area network (WAN) communications and/or virtual LAN communications and/or intranet communications and/or Internet communications to structures that couple thereto.

Bridging IHS 1304 may include a hypervisor 1745 that may create logical partition (LPAR) 1320-1, LPAR 1320-2, LPAR 1320-3, LPAR 1320-4, LPAR 1320-5, LPAR 1320-6 and LPAR 1320-7 in bridging IHS 1304. LPAR 1320-1, LPAR 1320-2 and LPAR 1320-3 may include virtual internal network adapter 1321-1, virtual internal network adapter 1321-2 and virtual internal network adapter 1321-3, respectively. Virtual internal network adapter 1321-1 and/or virtual internal network adapter 1321-2 and/or virtual internal network adapter 1321-3 may couple via channel 1322 to virtual internal network adapter 1323. Virtual internal network adapter 1323 may be referred to as bridge port 1323.

LPAR 1320-4 and LPAR 1320-5 may include virtual internal network adapter 1321-4 and virtual internal network adapter 1321-5, respectively. Virtual internal network adapter 1321-4 and/or virtual internal network adapter 1321-5 may couple via channel 1324 to virtual internal network adapter 1325. Virtual internal network adapter 1325 may be referred to as bridge port 1325.

LPAR 1320-6 and LPAR 1320-7 may include virtual internal network adapter 1321-6 and virtual internal network adapter 1321-7, respectively. Virtual internal network adapter 1321-6 and/or virtual internal network adapter 1321-7 may couple via channel 1326 to virtual internal network adapter 1327. Virtual internal network adapter 1327 may be referred to as bridge port 1327.

In one embodiment, virtual internal network adapters 1321-1, 1321-2, 1321-3, 1321-4, 1321-5, 1321-6, 1321-7, 1323, 1325 and 1327 may be internal queued direct (IQD) communication adapters. Channel 1322, channel 1324 and channel 1326 may be respective IQD communication networks internal to bridging IHS 1304.

Hypervisor 1745 may create virtual switch (VSWITCH) 1328, VSWITCH 1329 and VSWITCH 1330 in bridging IHS 1304. In one embodiment, VSWITCH 1328, 1329 and 1330 are each specialized LPARs. VSWITCH 1328 may include virtual internal network adapter 1323 and network adapter 1311. VSWITCH 1329 may include virtual internal network adapter 1325 and network adapter 1314. VSWITCH 1330 may include virtual internal network adapter 1327 and network adapter 1317.

FIG. 14 depicts one embodiment of HCM database 1400 in the disclosed bridging system 1300. HCM tool 600 may store the hardware configuration information in HCM database 1400 on a per adapter basis. In one embodiment, for each network adapter in bridging system 1300, HCM tool 600 may store, from the leftmost column to the rightmost column, the machine serial number (MSN), physical identification (PID), logical identification (LID), adapter type, logical partition (LPAR) access list, physical network identification (PNet ID) network adapter.

As shown in HCM database 1400, the hardware configuration information of adapter 1311 includes MSN of 0A0A0B11, PID of 0006, LID of 00F1, type of 0087, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter 1311 is located in physical channel 0006 in bridging IHS 1304 and may be identified logically by bridging IHS 1304 as 00F1. Adapter 1311 is a physical OSA network adapter and couples to NETWORK A 1312 on both ports 1 and 2. LPAR 1320-1, 1320-2 and 1320-3 of bridging IHS 1304 may access adapter 1311 to communicate via NETWORK A 1312.

The hardware configuration information of adapter 1314 includes MSN of 0A0A0B11, PID of 0007, LID of 00F5, type of 0087, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter 1314 is located in physical channel 0007 in bridging IHS 1304 and may be

identified logically by bridging IHS 1304 as 00F5. Adapter 1314 is a physical OSA network adapter and couples to NETWORK B 1315 on both ports 1 and 2. LPAR 1320-4 and 1320-5 of bridging IHS 1304 may access adapter 1314 to communicate via NETWORK B 1315.

The hardware configuration information of adapter 1317 includes MSN of 0A0A0B11, PID of 0008, LID of 00F8, type of 0087, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter 1317 is located in physical channel 0008 in bridging IHS 1304 and may be identified logically by bridging IHS 1304 as 00F8. Adapter 1317 is a physical OSA network adapter and couples to NETWORK C 1318 on both ports 1 and 2. LPAR 1320-6 and 1320-7 of bridging IHS 1304 may access adapter 1317 to communicate via NETWORK C 1318.

The hardware configuration information of adapter 1321-1 includes MSN of 0A0A0B11, PID of 0112, LID of 04C1, type of 008D, LPAR access list of 01, 02 and 03, and PNet ID 1 of NETA and PNet ID 2 with no entry because adapter 1321-1 is virtual and does not have a second port. In other words, adapter 1321-1 is a virtual adapter with a virtual channel 0112 in bridging IHS 1304 and may be identified logically by bridging IHS 1304 as 04C1. Adapter 1321-1 is an IQD virtual network adapter and couples to IQD network 1322 on virtual channel 0112. LPAR 1320-1, 1320-2 and 1320-3 of bridging IHS 1304 may access adapter 1321-1 to communicate via IQD network 1322. PNet ID 1 of NETA indicates that a bridging tool 1800 may bridge adapter 1321-1 with adapter 1311 to allow LPAR 1320-1, 1320-2 and 1320-3 to access adapter 1311 to communicate via NETWORK A 1312.

The hardware configuration information of adapter 1321-2 includes MSN of 0A0A0B11, PID of 0112, LID of 04C2, type of 008D, LPAR access list of 01, 02 and 03, and PNet ID 1 of NETA and PNet ID 2 with no entry because adapter 1321-2 is virtual and does not have a second port. In other words, adapter 1321-2 is a virtual adapter with a virtual channel 0112 in bridging IHS 1304 and may be identified logically by bridging IHS 1304 as 04C2. Adapter 1321-2 is an IQD virtual network adapter and couples to IQD network 1322 on virtual channel 0112. LPAR 1320-1, 1320-2 and 1320-3 of bridging IHS 1304 may access adapter 1321-2 to communicate via IQD network 1322. PNet ID 1 of NETA indicates that a bridging tool 1800 may bridge adapter 1321-2 with adapter 1311 to allow LPAR 1320-1, 1320-2 and 1320-3 to access adapter 1311 to communicate via NETWORK A 1312.

The hardware configuration information of adapter 1321-3 includes MSN of 0A0A0B11, PID of 0112, LID of 04C3, type of 008D, LPAR access list of 01, 02 and 03, and PNet ID 1 of NETA and PNet ID 2 with no entry because adapter 1321-3 is virtual and does not have a second port. In other words, adapter 1321-3 is a virtual adapter with a virtual channel 0112 in bridging IHS 1304 and may be identified logically by bridging IHS 1304 as 04C3. Adapter 1321-3 is an IQD virtual network adapter and couples to IQD network 1322 on virtual channel 0112. LPAR 1320-1, 1320-2 and 1320-3 of bridging IHS 1304 may access adapter 1321-3 to communicate via IQD network 1322. PNet ID 1 of NETA indicates that a bridging tool 1800 may bridge adapter 1321-3 with adapter 1311 to allow LPAR 1320-1, 1320-2 and 1320-3 to access adapter 1311 to communicate via NETWORK A 1312.

The hardware configuration information of adapter 1321-4 includes MSN of 0A0A0B11, PID of 0113, LID of 04C5, type of 008D, LPAR access list of 04 and 05, and PNet ID 1 of NETB and PNet ID 2 with no entry because adapter 1321-4

35

is virtual and does not have a second port. In other words, adapter **1321-4** is a virtual adapter with a virtual channel 0113 in bridging IHS **1304** and may be identified logically by bridging IHS **1304** as 04C5. Adapter **1321-4** is an IQD virtual network adapter and couples to IQD network **1324** on virtual channel 0113. LPAR **1320-4** and **1320-5** of bridging IHS **1304** may access adapter **1321-4** to communicate via IQD network **1324**. PNet ID 1 of NETB indicates that a bridging tool **1800** may bridge adapter **1321-4** with adapter **1311** to allow LPAR **1320-4** and **1320-5** to access adapter **1314** to communicate via NETWORK B **1315**.

The hardware configuration information of adapter **1321-5** includes MSN of 0A0A0B11, PID of 0113, LID of 04C6, type of 008D, LPAR access list of 04 and 05, and PNet ID 1 of NETB and PNet ID 2 with no entry because adapter **1321-5** is virtual and does not have a second port. In other words, adapter **1321-5** is a virtual adapter with a virtual channel 0113 in bridging IHS **1304** and may be identified logically by bridging IHS **1304** as 04C6. Adapter **1321-5** is an IQD virtual network adapter and couples to IQD network **1324** on virtual channel 0113. LPAR **1320-4** and **1320-5** of bridging IHS **1304** may access adapter **1321-5** to communicate via IQD network **1324**. PNet ID 1 of NETB indicates that a bridging tool **1800** may bridge adapter **1321-5** with adapter **1311** to allow LPAR **1320-4** and **1320-5** to access adapter **1314** to communicate via NETWORK B **1315**.

The hardware configuration information of adapter **1321-6** includes MSN of 0A0A0B11, PID of 0114, LID of 04C8, type of 008D, LPAR access list of 06 and 07, and PNet ID 1 of NETC and PNet ID 2 with no entry because adapter **1321-6** is virtual and does not have a second port. In other words, adapter **1321-6** is a virtual adapter with a virtual channel 0114 in bridging IHS **1304** and may be identified logically by bridging IHS **1304** as 04C8. Adapter **1321-6** is an IQD virtual network adapter and couples to IQD network **1326** on virtual channel 0114. LPAR **1320-6** and **1320-7** of bridging IHS **1304** may access adapter **1321-6** to communicate via IQD network **1326**. PNet ID 1 of NETC indicates that a bridging tool **1800** may bridge adapter **1321-6** with adapter **1311** to allow LPAR **1320-6** and **1320-7** to access adapter **1317** to communicate via NETWORK C **1318**.

The hardware configuration information of adapter **1321-7** includes MSN of 0A0A0B11, PID of 0114, LID of 04C9, type of 008D, LPAR access list of 06 and 07, and PNet ID 1 of NETC and PNet ID 2 with no entry because adapter **1321-7** is virtual and does not have a second port. In other words, adapter **1321-7** is a virtual adapter with a virtual channel 0114 in bridging IHS **1304** and may be identified logically by bridging IHS **1304** as 04C9. Adapter **1321-7** is an IQD virtual network adapter and couples to IQD network **1326** on virtual channel 0114. LPAR **1320-6** and **1320-7** of bridging IHS **1304** may access adapter **1321-7** to communicate via IQD network **1326**. PNet ID 1 of NETC indicates that a bridging tool **1800** may bridge adapter **1321-7** with adapter **1311** to allow LPAR **1320-6** and **1320-7** to access adapter **1317** to communicate via NETWORK C **1318**.

The hardware configuration information of adapter **1313** includes MSN of 0000F12A, PID of 0022, LID of 0DA1, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **1313** is located in physical channel 0022 in administered IHS **1306** and may be identified logically by administered IHS **1306** as 0DA1. Adapter **1313** is a physical OSA network adapter and couples to NETWORK A **1312** on both ports 1 and 2. Administered IHS **1306** may access adapter **1313** to communicate via NETWORK A **1312**.

36

The hardware configuration information of adapter **1316** includes MSN of DDD32AA, PID of 0054, LID of 00C1, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **1316** is located in physical channel 0054 in administered IHS **1308** and may be identified logically by administered IHS **1308** as 00C1. Adapter **1316** is a physical OSA network adapter and couples to NETWORK B **1315** on both ports 1 and 2. Administered IHS **1308** may access adapter **1316** to communicate via NETWORK B **1315**.

The hardware configuration information of adapter **1319** includes MSN of 000000B2, PID of 0001, LID of 0DD4, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **1319** is located in physical channel 0001 in administered IHS **1310** and may be identified logically by administered IHS **1310** as 0DD4. Adapter **1319** is a physical OSA network adapter and couples to NETWORK C **1318** on both ports 1 and 2. Administered IHS **1310** may access adapter **1319** to communicate via NETWORK C **1318**.

As illustrated in FIG. 13, in the HCM database **1400** of FIG. 14 IQD adapters **1321-6** and **1321-7** exhibit a PNet ID of NETC. This indicates to bridging tool **1800** (not shown in FIG. 13, but shown in FIG. 18) that the internal network IQD **1326** should be bridged to an external network (NETWORK C) that exhibits the same PNet ID as internal network IQD **1326**. More particularly, bridging tool **1800** may bridge internal networks, i.e. networks internal to bridging IHS **1304**, to external networks with a matching PNet ID. In one embodiment, an internal network (e.g. IQD **1426**) is not assigned a PNet ID in the HCM database **1400** unless the internal network should be bridged to an external network, such as OSA **1317** that exhibits a matching PNet ID. In this particular example, OSA **1317** exhibits a PNet ID of NETC and IQD internal network IQD **1326** also exhibits the same PNet ID of NETC. In response to this match of PNet IDs, bridging tool **1800** may bridge the connection between IQD **1326** and OSA **1317**, thus providing IQD **1326** with access to external NETWORK C. Without this bridge, provided by bridge port **1327** and (VSWITCH) **1330**, IQD channels are only internal and not externally connected, in one embodiment. In one embodiment, an internal network such as IQD **1326** is not provided with a PNet ID unless that internal network is to be bridged with an external network.

FIG. 15 is a block diagram showing one embodiment of the disclosed bridging system **1500** utilizing PNet IDs. Bridging system **1500** may utilize network adapter **1501**, administrative network **1502** and network adapter **1503** to couple HCM IHS **500** to administered IHS **1504**. Administered IHS **1504** may be referred to as bridging IHS **1504**. Bridging system **1500** may utilize network adapter **1501**, administrative network **1502** and network adapter **1505** to couple HCM IHS **500** to administered IHS **1506**. Bridging system **1500** may utilize network adapter **1501**, administrative network **1502** and network adapter **1507** to couple HCM IHS **500** to administered IHS **1508**. Administered IHSs **1504**, **1506** and **1508** couple via administrative network **1502** to HCM IHS **500** to enable HCM IHS **500** to administer HCM database **1600** with HCM tool **600** to the administered IHSs.

Bridging system **1500** may utilize network adapter **1509** via NETWORK A **1510** via network adapter **1511** to couple bridging IHS **1504** to administered IHS **1506**. Bridging system **1500** may utilize network adapter **1512** via NETWORK B **1513** via network adapter **1514** to couple bridging IHS **1504** to administered IHS **1508**.

In one embodiment, network adapters **1501**, **1503**, **1505** and **1507** may be Ethernet (ETH) adapters. Network adapters

1509, **1511**, **1512** and **1514** may be open system adapters (OSAs). In one embodiment, administrative network **1502**, NETWORK A **1510** and NETWORK B **1513** may provide local area network (LAN) communications and/or wide area network (WAN) communications and/or virtual LAN communications and/or intranet communications and/or Internet communications to structures that couple thereto.

Bridging IHS **1504** may include a hypervisor **1745** that may create logical partition (LPAR) **1515-1**, LPAR **1515-2**, LPAR **1515-3**, LPAR **1515-4**, LPAR **1515-5**, LPAR **1515-6** and LPAR **1515-7** in bridging IHS **1504**. LPAR **1515-1**, LPAR **1515-2** and LPAR **1515-3** may include virtual internal network adapter **1516-1**, virtual internal network adapter **1516-2** and virtual internal network adapter **1516-3**, respectively. Virtual internal network adapter **1516-1** and/or virtual internal network adapter **1516-2** and/or virtual internal network adapter **1516-3** may couple via channel **1517** to virtual internal network adapter **1518**. Virtual internal network adapter **1518** may be referred to as bridge port **1518**.

LPAR **1515-4**, LPAR **1515-5**, LPAR **1515-6** and LPAR **1515-7** may include virtual internal network adapter **1516-4**, virtual internal network adapter **1516-5**, virtual internal network adapter **1516-6** and virtual internal network adapter **1516-7**, respectively. Virtual internal network adapter **1516-4** and/or virtual internal network adapter **1516-5** and/or virtual internal network adapter **1516-6** and/or virtual internal network adapter **1516-7** may couple via channel **1519** to virtual internal network adapter **1520**. Virtual internal network adapter **1520** may be referred to as bridge port **1520**.

In one embodiment, virtual internal network adapters **1516-1**, **1516-2**, **1516-3**, **1516-4**, **1516-5**, **1516-6**, **1516-7**, **1518** and **1519** may be internal queued direct (IQD) communication adapters. Channel **1517** and channel **1519** may be respective IQD communication networks internal to bridging IHS **1504**.

Hypervisor **1745** in bridging IHS **1504** may create virtual switch (VSWITCH) **1521** and VSWITCH **1522** in bridging IHS **1504**. In one embodiment, VSWITCH **1521** and **1522** are each specialized LPARs. VSWITCH **1521** may include virtual internal network adapter **1518** and network adapter **1509**. VSWITCH **1522** may include virtual internal network adapter **1520** and network adapter **1512**.

In one embodiment, administered IHS **1508** may be a bridging IHS. Administered IHS **1508** may include a hypervisor **1745** that may create LPAR **1523-1** and LPAR **1523-2** in administered IHS **1508**. LPAR **1523-1** and LPAR **1523-2** may include virtual internal network adapter **1524-1** and virtual internal network adapter **1524-2**, respectively. Virtual internal network adapter **1524-1** and/or virtual internal network adapter **1524-2** may couple via channel **1525** to virtual internal network adapter **1526**. Virtual internal network adapter **1526** may be referred to as bridge port **1526**.

In one embodiment, virtual internal network adapters **1524-1** and **1524-2** may be internal queued direct (IQD) communication adapters. Channel **1525** may be an IQD communication network internal to administered IHS **1508**. Hypervisor **1745** in administered IHS **1508** may create virtual switch (VSWITCH) **1527** in administered IHS **1508**. In one embodiment, VSWITCH **1527** may be a specialized LPAR. VSWITCH **1527** may include virtual internal network adapter **1526** and network adapter **1514**.

FIG. 16 depicts one embodiment of HCM database **1600** in the disclosed bridging system **1500**. HCM tool **600** may store the hardware configuration information in HCM database **1600** on a per adapter basis. In one embodiment, for each network adapter in bridging system **1500**, HCM tool **600** may store, from the leftmost column to the rightmost column, the

machine serial number (MSN), physical identification (PID), logical identification (LID), adapter type, logical partition (LPAR) access list, physical network identification (PNet ID) network adapter.

As shown in HCM database **1600**, the hardware configuration information of adapter **1509** includes MSN of 03F00A21, PID of 0006, LID of 00F1, type of 0087, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **1509** is located in physical channel 0006 in bridging IHS **1504** and may be identified logically by bridging IHS **1504** as 00F1. Adapter **1509** is a physical OSA network adapter and couples to NETWORK A **1510** on both ports 1 and 2. LPAR **1515-1**, **1515-2** and **1515-3** of bridging IHS **1504** may access adapter **1509** to communicate via NETWORK A **1510**.

The hardware configuration information of adapter **1512** includes MSN of 03F00A21, PID of 0007, LID of 00F5, type of 0087, LPAR access list of 04, 05, 06 and 07, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **1512** is located in physical channel 0007 in bridging IHS **1504** and may be identified logically by bridging IHS **1504** as 00F5. Adapter **1512** is a physical OSA network adapter and couples to NETWORK B **1513** on both ports 1 and 2. LPAR **1515-4**, **1515-5**, **1515-6** and **1515-7** of bridging IHS **1504** may access adapter **1512** to communicate via NETWORK B **1513**.

The hardware configuration information of adapter **1516-1** includes MSN of 03F00A21, PID of 0111, LID of 04C0, type of 008D, LPAR access list of 01, 02 and 03, and PNet ID 1 of NETA and PNet ID 2 with no entry because adapter **1516-1** is virtual and does not have a second port. In other words, adapter **1516-1** is a virtual adapter with a virtual channel 0111 in bridging IHS **1504** and may be identified logically by bridging IHS **1504** as 04C0. Adapter **1516-1** is an IQD virtual network adapter and couples to IQD network **1517** on virtual channel 0111. LPAR **1515-1**, **1515-2** and **1515-3** of bridging IHS **1504** may access adapter **1516-1** to communicate via IQD network **1517**. PNet ID 1 of NETA indicates that a bridging tool **1800** may bridge adapter **1516-1** with adapter **1509** to allow LPAR **1515-1**, **1515-2** and **1515-3** to access adapter **1509** to communicate via NETWORK A **1510**.

The hardware configuration information of adapter **1516-2** includes MSN of 03F00A21, PID of 0111, LID of 04C1, type of 008D, LPAR access list of 01, 02 and 03, and PNet ID 1 of NETA and PNet ID 2 with no entry because adapter **1516-2** is virtual and does not have a second port. In other words, adapter **1516-2** is a virtual adapter with a virtual channel 0111 in bridging IHS **1504** and may be identified logically by bridging IHS **1504** as 04C1. Adapter **1516-2** is an IQD virtual network adapter and couples to IQD network **1517** on virtual channel 0111. LPAR **1515-1**, **1515-2** and **1515-3** of bridging IHS **1504** may access adapter **1516-2** to communicate via IQD network **1517**. PNet ID 1 of NETA indicates that a bridging tool **1800** may bridge adapter **1516-2** with adapter **1509** to allow LPAR **1515-1**, **1515-2** and **1515-3** to access adapter **1509** to communicate via NETWORK A **1510**.

The hardware configuration information of adapter **1516-3** includes MSN of 03F00A21, PID of 0111, LID of 04C2, type of 008D, LPAR access list of 01, 02 and 03, and PNet ID 1 of NETA and PNet ID 2 with no entry because adapter **1516-3** is virtual and does not have a second port. In other words, adapter **1516-3** is a virtual adapter with a virtual channel 0111 in bridging IHS **1504** and may be identified logically by bridging IHS **1504** as 04C2. Adapter **1516-3** is an IQD virtual network adapter and couples to IQD network **1517** on virtual channel 0111. LPAR **1515-1**, **1515-2** and **1515-3** of bridging IHS **1504** may access adapter **1516-3** to communicate via IQD network **1517**. PNet ID 1 of NETA indicates that a

bridging tool **1800** may bridge adapter **1516-3** with adapter **1509** to allow LPAR **1515-1**, **1515-2** and **1515-3** to access adapter **1509** to communicate via NETWORK A **1510**.

The hardware configuration information of adapter **1516-4** includes MSN of 03F00A21, PID of 0112, LID of 04C4, type of 008D, LPAR access list of 04, 05, 06 and 07, and PNet ID 1 of NETB and PNet ID 2 with no entry because adapter **1516-4** is virtual and does not have a second port. In other words, adapter **1516-4** is a virtual adapter with a virtual channel 0112 in bridging IHS **1504** and may be identified logically by bridging IHS **1504** as 04C4. Adapter **1516-4** is an IQD virtual network adapter and couples to IQD network **1519** on virtual channel 0112. LPAR **1515-4**, **1515-5**, **1515-6** and **1515-7** of bridging IHS **1504** may access adapter **1516-4** to communicate via IQD network **1519**. PNet ID 1 of NETB indicates that a bridging tool **1800** may bridge adapter **1516-4** with adapter **1512** to allow LPAR **1515-4**, **1515-5**, **1515-6** and **1515-7** to access adapter **1512** to communicate via NETWORK B **1513**.

The hardware configuration information of adapter **1516-5** includes MSN of 03F00A21, PID of 0112, LID of 04C5, type of 008D, LPAR access list of 04, 05, 06 and 07, and PNet ID 1 of NETB and PNet ID 2 with no entry because adapter **1516-5** is virtual and does not have a second port. In other words, adapter **1516-5** is a virtual adapter with a virtual channel 0112 in bridging IHS **1504** and may be identified logically by bridging IHS **1504** as 04C5. Adapter **1516-5** is an IQD virtual network adapter and couples to IQD network **1519** on virtual channel 0112. LPAR **1515-4**, **1515-5**, **1515-6** and **1515-7** of bridging IHS **1504** may access adapter **1516-5** to communicate via IQD network **1519**. PNet ID 1 of NETB indicates that a bridging tool **1800** may bridge adapter **1516-5** with adapter **1512** to allow LPAR **1515-4**, **1515-5**, **1515-6** and **1515-7** to access adapter **1512** to communicate via NETWORK B **1513**.

The hardware configuration information of adapter **1516-6** includes MSN of 03F00A21, PID of 0112, LID of 04C6, type of 008D, LPAR access list of 04, 05, 06 and 07, and PNet ID 1 of NETB and PNet ID 2 with no entry because adapter **1516-6** is virtual and does not have a second port. In other words, adapter **1516-6** is a virtual adapter with a virtual channel 0112 in bridging IHS **1504** and may be identified logically by bridging IHS **1504** as 04C6. Adapter **1516-6** is an IQD virtual network adapter and couples to IQD network **1519** on virtual channel 0112. LPAR **1515-4**, **1515-5**, **1515-6** and **1515-7** of bridging IHS **1504** may access adapter **1516-6** to communicate via IQD network **1519**. PNet ID 1 of NETB indicates that a bridging tool **1800** may bridge adapter **1516-6** with adapter **1512** to allow LPAR **1515-4**, **1515-5**, **1515-6** and **1515-7** to access adapter **1512** to communicate via NETWORK B **1513**.

The hardware configuration information of adapter **1516-7** includes MSN of 03F00A21, PID of 0112, LID of 04C7, type of 008D, LPAR access list of 04, 05, 06 and 07, and PNet ID 1 of NETB and PNet ID 2 with no entry because adapter **1516-7** is virtual and does not have a second port. In other words, adapter **1516-7** is a virtual adapter with a virtual channel 0112 in bridging IHS **1504** and may be identified logically by bridging IHS **1504** as 04C7. Adapter **1516-7** is an IQD virtual network adapter and couples to IQD network **1519** on virtual channel 0112. LPAR **1515-4**, **1515-5**, **1515-6** and **1515-7** of bridging IHS **1504** may access adapter **1516-7** to communicate via IQD network **1519**. PNet ID 1 of NETB indicates that a bridging tool **1800** may bridge adapter **1516-7** with adapter **1512** to allow LPAR **1515-4**, **1515-5**, **1515-6** and **1515-7** to access adapter **1512** to communicate via NETWORK B **1513**.

The hardware configuration information of adapter **1511** includes MSN of 2338282D, PID of 0031, LID of 00F3, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **1511** is located in physical channel 0031 in administered IHS **1506** and may be identified logically by administered IHS **1506** as 00F3. Adapter **1511** is a physical OSA network adapter and couples to NETWORK A **1510** on both ports 1 and 2. Administered IHS **1506** may access adapter **1511** to communicate via NETWORK A **1510**.

The hardware configuration information of adapter **1514** includes MSN of 2338282D, PID of 0022, LID of 0DA1, type of 0087, LPAR access list of 01 and 02, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **1514** is located in physical channel 0022 in bridging IHS **1508** and may be identified logically by bridging IHS **1508** as 0DA1. Adapter **1514** is a physical OSA network adapter and couples to NETWORK B **1513** on both ports 1 and 2. LPAR **1515-1** and **1515-2** of bridging IHS **1508** may access adapter **1514** to communicate via NETWORK B **1513**.

The hardware configuration information of adapter **1524-1** includes MSN of 2338282D, PID of 0200, LID of 06D1, type of 008D, LPAR access list of 01 and 02, and PNet ID 1 of NETB and PNet ID 2 with no entry because adapter **1524-1** is virtual and does not have a second port. In other words, adapter **1524-1** is a virtual adapter with a virtual channel 0200 in bridging IHS **1508** and may be identified logically by bridging IHS **1508** as 06D1. Adapter **1524-1** is an IQD virtual network adapter and couples to IQD network **1525** on virtual channel 0200. LPAR **1523-1** and **1523-2** of bridging IHS **1508** may access adapter **1524-1** to communicate via IQD network **1525**. PNet ID 1 of NETB indicates that a bridging tool **1800** may bridge adapter **1524-1** with adapter **1514** to allow LPAR **1523-1** and **1523-2** to access adapter **1514** to communicate via NETWORK B **1513**.

The hardware configuration information of adapter **1524-2** includes MSN of 2338282D, PID of 0200, LID of 06D2, type of 008D, LPAR access list of 01 and 02, and PNet ID 1 of NETB and PNet ID 2 with no entry because adapter **1524-2** is virtual and does not have a second port. In other words, adapter **1524-2** is a virtual adapter with a virtual channel 0200 in bridging IHS **1508** and may be identified logically by bridging IHS **1508** as 06D2. Adapter **1524-2** is an IQD virtual network adapter and couples to IQD network **1525** on virtual channel 0200. LPAR **1523-1** and **1523-2** of bridging IHS **1508** may access adapter **1524-2** to communicate via IQD network **1525**. PNet ID 1 of NETB indicates that a bridging tool **1800** may bridge adapter **1524-2** with adapter **1514** to allow LPAR **1523-1** and **1523-2** to access adapter **1514** to communicate via NETWORK B **1513**.

FIG. 17 is a block diagram of a bridging information handling system (IHS) **1700** that may be used in the disclosed bridging system. With respect to FIG. 11, like numbers indicate like elements. Bridging IHS **1700** includes a processor **1705** that may include multiple cores. RNIC converging IHS **1700** processes, transfers, communicates, modifies, stores or otherwise handles information in digital form, analog form or other form. In one embodiment, bridging IHS **1700** includes a bus **1710**, i.e. channel **1710**. In another embodiment, bus **1710** may be multiple busses, i.e., multiple channels. Bus **1710** may couple processor **1705** to memory **1715** via a memory controller **1720** and memory bus **1725**. System memory **1715** may also be referred to as main memory. System memory **1715** may be a static random access memory (SRAM) array or a dynamic random access memory (DRAM) array. Processor **1705** may also include local memory such as L1, L2 and L3 caches.

In one embodiment, a video graphics controller **1730** couples display **1735** to bus **1710**. In another embodiment, bridging IHS **1700** may operate without display **1735** and/or video graphics controller **1730**. Nonvolatile storage **1740**, such as a hard disk drive, solid-state drive (SSD), CD drive, DVD drive, or other nonvolatile storage couples to bus **1710** to provide bridging IHS **1700** with permanent storage of information. System memory **1715** and nonvolatile storage **1740** are both forms of memory stores. In one embodiment, nonvolatile storage **1740** stores a hypervisor **1745** (HYPERVISOR) that governs operation of bridging IHS **1700**. In another embodiment, nonvolatile storage **1740** may store an operating system (not shown) that governs operation of bridging IHS **1700**. In another embodiment, nonvolatile storage **1740** may store an operating system (not shown) that governs operation of bridging IHS **1700**, where the operating system includes a hypervisor (not shown).

I/O devices **1750**, such as speakers, a keyboard and a pointing device, may couple to bus **1710** via I/O controller **1755** and I/O bus **1760**. One or more expansion busses **1765**, i.e. channels **1765**, such as USB, IEEE 1394 bus, ATA, SATA, PCI, PCIE, DVI, HDMI and other busses, i.e. channels, couple to bus **1710** to facilitate the connection of peripherals and devices to bridging IHS **1700**. Network interface controllers (NICs), for example, NIC **1770-1**, NIC **1770-2**, . . . , NIC **1770-L**, wherein L is the number of NICs, may couple to bus **1710** to enable bridging IHS **1700** to connect by wire or wirelessly to a network and other information handling systems. NIC **1770-1**, NIC **1770-2**, . . . , NIC **1770-L** may also be called a network communication adapter, network interface adapter, network adapter, network interface or an adapter. NIC **1770-1**, NIC **1770-2**, . . . , NIC **1770-L** may take many forms. For example, NIC **1770-1**, NIC **1770-2**, . . . , NIC **1770-L** may take the form of an Ethernet (ETH) adapter, open systems adapter (OSA), RDMA enabled network interface controller (RNIC) or other network communication adapter.

While FIG. **17** shows one IHS that employs processor **1705**, the IHS may take many forms. For example, bridging IHS **1700** may take the form of a mainframe, server, central processor complex (CPC), desktop, portable, laptop, notebook, tablet or other form factor computer or data processing system. Bridging IHS **1700** may take other form factors such as a gaming device, a personal digital assistant (PDA), a portable telephone device, a communication device or other devices that include a processor and memory.

Bridging IHS **1700** includes a bridging tool computer program product **1800** on digital media **1775** such as a CD, DVD or other media. For simplicity, the term bridging tool will be used below. Bridging IHS **1700** may store bridging tool **1800** in nonvolatile storage **1740** as bridging tool **1800'**. Bridging IHS **1700** may also store hypervisor **1745** (HYPERVISOR) and logical partition (LPAR) **1780-1**, LPAR **1780-2**, . . . , LPAR **1780-K**, wherein K is the number of LPARs, in nonvolatile storage **1740**.

In another embodiment, bridging tool **1800'** may be part of the hypervisor **1745** (not shown). In another embodiment, bridging tool **1800'** may be in LPAR **1780-1**, LPAR **1780-2**, . . . , LPAR **1780-K**. In another embodiment, bridging IHS **1700** may store an operating system (not shown) that governs operation of bridging IHS **1700**, where the operating system includes a hypervisor (not shown) and where the operating system includes LPAR **1780-1**, LPAR **1780-2**, . . . , LPAR **1780-K** as virtual machines (not shown). When bridging IHS **1700** initializes, the IHS loads hypervisor **1745** into system memory **1715** for execution as hypervisor **1745'**. Bridging IHS **1700** also loads bridging tool **1800'** into system memory **1715** for execution as bridging tool **1800''**. Bridging

IHS **1700** may also load LPAR **1780-1**, LPAR **1780-2**, . . . , LPAR **1780-K** into system memory **1715** for execution as LPAR **1780-1'**, LPAR **1780-2'**, . . . , LPAR **1780-K'**, respectively.

In another embodiment, when bridging IHS **1700** initializes, the IHS may load an operating system (not shown) into system memory **1715** for execution. In another embodiment, when bridging IHS **1700** initializes, the IHS may load an operating system (not shown) that includes a hypervisor (not shown) and includes LPAR **1780-1**, LPAR **1780-2**, . . . , LPAR **1780-K** as virtual machines (not shown) into system memory **1715** for execution.

FIG. **18** is a flowchart that shows a representative process flow of a bridging tool **1800** that may be used in the disclosed bridging system. Process flow commences when bridging tool **1800** in bridging IHS **1700** initializes, as per block **1805**. If HCM tool **600** in HCM IHS **500** does not transmit HCM database **580**, as per decision block **1810**, process flow continues at decision block **1810**. If HCM tool **600** in HCM IHS **500** does transmit HCM database **580**, as per decision block **1810**, a hypervisor agent in bridging IHS **1700** may receive HCM database **580**, as per block **1815**. In one embodiment, the hypervisor agent in the bridging IHS **1700** is included in hypervisor **1745**.

The hypervisor agent may allow hypervisor **1745** to access HCM database **580**. Hypervisor **1745** may transmit HCM database **580** to bridging tool **1800**, as per block **1820**. Bridging tool **1800** may extract the hardware configuration information of bridging IHS **1700** from the HCM database **580**, as per block **1825**. In one embodiment, the hardware configuration information of bridging IHS **1700** from HCM database **580** may include, but is not limited to, on a per adapter basis, machine serial numbers (MSNs), physical identifications (PIDs), logical identifications (LIDs), adapter types, a logical partition (LPAR) access list, a physical network identification (PNet ID) of the first port of the adapter and a PNet ID of the second port of the adapter. In one embodiment, the adapter type "0087" may be an OSA adapter and the adapter type "008D" may be an internal queued direct (IQD) communication adapter.

In one embodiment, the bridging tool **1800** may share the extracted hardware configuration information of bridging IHS **1700** with hypervisor **1745**. Hypervisor **1745** may update the hardware configuration of bridging IHS **1700** with the extracted hardware configuration information of bridging IHS **1700**. In another embodiment, the bridging tool **1800** may share the extracted hardware configuration information of bridging IHS **1700** with LPARs **1780-1**, **1780-2**, . . . , **1780-K**, where K is the number of LPARs in bridging IHS **1700**. LPARs **1780-1**, **1780-2**, . . . , **1780-K** may update their respective hardware configuration with the extracted hardware configuration information of bridging IHS **1700**.

Bridging tool **1800** may sort the extracted hardware configuration information by PNet IDs, as per block **1830**. For example, the bridging tool **1800** may list all adapters with the PNet ID of "NETA" first, followed by all adapters with the PNet ID of "NETB". Bridging tool **1800** may further sort the extracted configuration information by adapter type, as per block **1835**. For example, the bridging tool **1800** may list all adapters with the type "0087" and the PNet ID "NETA" first, followed by the adapters with the type "008D" and the PNet ID of "NETA", further followed by the adapters with the type "0087" and the PNet ID of "NETB".

Bridging tool **1800** may determine if any adapters may be bridged, as per decision block **1840**. In one embodiment, bridging tool **1800** may bridge adapters with the type "008D", i.e. IQD, with adapters of the type "0087", i.e. OSA, if the

IQD adapter's PNet ID matches the OSA's PNet ID. If bridging tool **1800** determines that bridging IHS **1700** contains bridgeable adapters, as per block **1840**, bridging tool **1800** may bridge communications between IQD adapters and OSAs that have matching PNet IDs, as per block **1845**. For example, as shown in FIGS. **13** and **14**, virtual internal network adapter **1321-7** is of type "008D", i.e. IQD, and has a PNet ID of "NETC". Network adapter **1317** is of type "007", i.e. OSA, and has a PNet ID of "NETC".

Bridging tool **1800** may bridge communications between virtual internal network adapter **1321-7** and network adapter **1317**. In one embodiment, virtual internal network adapter **1321-7** and bridge port **1327** are coupled. To bridge communications between virtual internal network adapter **1321-7** and network adapter **1317**, bridging tool **1800** may bridge communications from bridge port **1327**, through VSWITCH **1330**, to network adapter **1327**. In one embodiment, LPAR **1320-7** may then communicate over the bridge between virtual internal network adapter **1321-7** and network adapter **1317** to any IHS on NETWORK C **1318**, as per block **1850**.

Process flow terminates at end block **1855**. If bridging tool **1800** determines that no adapters on bridging IHS **1700** may be bridged, as per decision block **1840**, process flow terminates at end block **1855**. Alternatively, process flow may continue at start block **1805**.

IV. Load Balancing System

FIG. **19** is a block diagram showing one embodiment of the disclosed load balancing system **1900** utilizing PNet IDs. Load balancing system **1900** may utilize network adapter **1901**, administrative network **1902** and network adapter **1903** to couple HCM IHS **500** to administered IHS **1904**. Administered IHS **1904** may also be referred to as load balancing IHS **1904**. Load balancing system **1900** may utilize network adapter **1901**, administrative network **1902** and network adapter **1905** to couple HCM IHS **500** to administered IHS **1906**. Load balancing system **1900** may utilize network adapter **1901**, administrative network **1902** and network adapter **1907** to couple HCM IHS **500** to administered IHS **1908**. Load balancing system **1900** may utilize network adapter **1901**, administrative network **1902** and network adapter **1909** to couple HCM IHS **500** to administered IHS **1910**. Administered IHSs **1904**, **1906**, **1908** and **1910** couple via administrative network **1902** to HCM IHS **500** to enable HCM IHS **500** to administer HCM database **2000** with HCM tool **600** to the administered IHSs.

Load balancing system **1900** may utilize network adapter **1911** and/or network adapter **1912** and/or network adapter **1913** and/or network adapter **1914** via NETWORK A **1915** via network adapter **1916** and/or network adapter **1917** and/or network adapter **1918** and/or network adapter **1919** to couple load balancing IHS **1904** to administered IHS **1906**. Load balancing system **1900** may utilize network adapter **1920** and/or network adapter **1921** and/or network adapter **1922** and/or network adapter **1923** via NETWORK B **1924** via network adapter **1925** and/or network adapter **1926** and/or network adapter **1927** and/or network adapter **1928** to couple load balancing IHS **1904** to administered IHS **1906**. Load balancing system **1900** may utilize network adapter **1929** and/or network adapter **1930** and/or network adapter **1931** and/or network adapter **1932** via NETWORK C **1933** via network adapter **1934** and/or network adapter **1935** and/or network adapter **1936** and/or network adapter **1937** to couple load balancing IHS **1904** to administered IHS **1910**.

In one embodiment, network adapter **1901**, **1903**, **1905**, **1907** and **1909** may be Ethernet (ETH) adapters. Network adapters **1911**, **1912**, **1916**, **1918**, **1920**, **1921**, **1925**, **1927**, **1929**, **1930**, **1934** and **1936** may be open system adapters

(OSAs). Network adapters **1913**, **1914**, **1917**, **1919**, **1922**, **1923**, **1926**, **1928**, **1931**, **1933**, **1935** and **1937** may be remote direct memory access (RDMA) enabled network adapter controllers (RNICs). In one embodiment, administrative network **1902**, NETWORK A **1915**, NETWORK B **1924** and NETWORK C **1933** may provide local area network (LAN) communications and/or wide area network (WAN) communications and/or virtual LAN communications and/or intranet communications and/or Internet communications to structures that couple thereto.

Load balancing IHS **1904** may include a hypervisor (not shown) that may create logical partition (LPAR) **1938-1**, LPAR **1938-2**, LPAR **1938-3**, LPAR **1938-4**, LPAR **1938-5**, LPAR **1938-6** and LPAR **1938-7** in load balancing IHS **1904**. LPAR **1938-1**, LPAR **1938-2** and LPAR **1938-3** may include virtual network adapter **1939-1**, virtual network adapter **1939-2** and virtual network adapter **1939-3**, respectively. Virtual network adapter **1939-1**, virtual network adapter **1939-2** and virtual network adapter **1939-3** may couple to network adapter **1911** and network adapter **1912** via a channel, i.e., a bus. LPAR **1938-4** and LPAR **1938-5** may include virtual network adapter **1939-4** and virtual network adapter **1939-5**, respectively. Virtual network adapter **1939-4** and virtual network adapter **1939-5** may couple to network adapter **1920** and network adapter **1921** via a channel. LPAR **1938-6** and LPAR **1938-7** may include virtual network adapter **1939-6** and virtual network adapter **1939-7**, respectively. Virtual network adapter **1939-6** and virtual network adapter **1939-7** may couple to network adapter **1929** and network adapter **1930** via a channel.

LPAR **1938-1**, LPAR **1938-2** and LPAR **1938-3** may include virtual network adapter **1940-1**, virtual network adapter **1940-2** and virtual network adapter **1940-3**, respectively. Virtual network adapter **1940-1**, virtual network adapter **1940-2** and virtual network adapter **1940-3** may couple to network adapter **1913** and network adapter **1914** via a channel. LPAR **1938-4** and LPAR **1938-5** may include virtual network adapter **1940-4** and virtual network adapter **1940-5**, respectively. Virtual network adapter **1940-4** and virtual network adapter **1940-5** may couple to network adapter **1922** and network adapter **1923** via a channel. LPAR **1938-6** and LPAR **1938-7** may include virtual network adapter **1940-6** and virtual network adapter **1940-7**, respectively. Virtual network adapter **1940-6** and virtual network adapter **1940-7** may couple to network adapter **1931** and network adapter **1932** via a channel.

FIG. **20** depicts one embodiment of HCM database **2000** in the disclosed load balancing system **1900**. HCM tool **600** may store the hardware configuration information in HCM database **2000** on a per adapter basis. In one embodiment, for each network adapter in load balancing system **1900**, HCM tool **600** may store, from the leftmost column to the rightmost column, the machine serial number (MSN), physical identification (PID), logical identification (LID), adapter type, logical partition (LPAR) access list, physical network identification (PNet ID) network adapter.

As shown in HCM database **2000**, the hardware configuration information of adapter **1911** includes MSN of 0000FFA1, PID of 0006, LID of 00F1, type of 0087, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **1911** is located in physical channel 0006 in load balancing IHS **1904** and may be identified logically by load balancing IHS **1904** as 00F1. Adapter **1911** is a physical OSA network adapter and couples to NETWORK A **1915** on both ports 1 and 2. LPAR **1938-1**, **1938-2** and **1938-3** of load balancing IHS **1904** may access adapter **1911** to communicate via NETWORK A **1915**.

The hardware configuration information of adapter **1912** includes MSN of 0000FFA1, PID of 0007, LID of 00F5, type of 0087, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **1912** is located in physical channel 0007 in load balancing IHS **1904** and may be identified logically by load balancing IHS **1904** as 00F5. Adapter **1912** is a physical OSA network adapter and couples to NETWORK A **1915** on both ports 1 and 2. LPAR **1938-1**, **1938-2** and **1938-3** of load balancing IHS **1904** may access adapter **1912** to communicate via NETWORK A **1915**.

The hardware configuration information of adapter **1913** includes MSN of 0000FFA1, PID of 0111, LID of 04C0, type of 0008, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **1913** is located in physical channel 0111 in load balancing IHS **1904** and may be identified logically by load balancing IHS **1904** as 04C0. Adapter **1913** is a physical RNIC network adapter and couples to NETWORK A **1915** on both ports 1 and 2. LPAR **1938-1**, **1938-2** and **1938-3** of load balancing IHS **1904** may access adapter **1913** to communicate via NETWORK A **1915**.

The hardware configuration information of adapter **1914** includes MSN of 0000FFA1, PID of 0112, LID of 04C4, type of 0008, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **1914** is located in physical channel 0112 in load balancing IHS **1904** and may be identified logically by load balancing IHS **1904** as 04C4. Adapter **1914** is a physical RNIC network adapter and couples to NETWORK A **1915** on both ports 1 and 2. LPAR **1938-1**, **1938-2** and **1938-3** of load balancing IHS **1904** may access adapter **1914** to communicate via NETWORK A **1915**.

The hardware configuration information of adapter **1920** includes MSN of 0000FFA1, PID of 0008, LID of 00F9, type of 0087, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **1920** is located in physical channel 0008 in load balancing IHS **1904** and may be identified logically by load balancing IHS **1904** as 00F9. Adapter **1920** is a physical OSA network adapter and couples to NETWORK B **1924** on both ports 1 and 2. LPAR **1938-4** and **1938-5** of load balancing IHS **1904** may access adapter **1920** to communicate via NETWORK B **1924**.

The hardware configuration information of adapter **1921** includes MSN of 0000FFA1, PID of 0009, LID of 00FC, type of 0087, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **1921** is located in physical channel 0009 in load balancing IHS **1904** and may be identified logically by load balancing IHS **1904** as 00FC. Adapter **1921** is a physical OSA network adapter and couples to NETWORK B **1924** on both ports 1 and 2. LPAR **1938-4** and **1938-5** of load balancing IHS **1904** may access adapter **1921** to communicate via NETWORK B **1924**.

The hardware configuration information of adapter **1922** includes MSN of 0000FFA1, PID of 0113, LID of 04C8, type of 0008, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **1922** is located in physical channel 0113 in load balancing IHS **1904** and may be identified logically by load balancing IHS **1904** as 04C8. Adapter **1922** is a physical RNIC network adapter and couples to NETWORK B **1924** on both ports 1 and 2. LPAR **1938-4** and **1938-5** of load balancing IHS **1904** may access adapter **1922** to communicate via NETWORK B **1924**.

The hardware configuration information of adapter **1923** includes MSN of 0000FFA1, PID of 0114, LID of 04CB, type of 0008, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **1923** is located in physical channel 0114 in load balancing IHS **1904** and may be identified logically by load balancing IHS **1904** as 04CB. Adapter **1923** is a physical RNIC network adapter and

couples to NETWORK B **1924** on both ports 1 and 2. LPAR **1938-4** and **1938-5** of load balancing IHS **1904** may access adapter **1923** to communicate via NETWORK B **1924**.

The hardware configuration information of adapter **1929** includes MSN of 0000FFA1, PID of 000A, LID of 00FF, type of 0087, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **1929** is located in physical channel 000A in load balancing IHS **1904** and may be identified logically by load balancing IHS **1904** as 00FF. Adapter **1929** is a physical OSA network adapter and couples to NETWORK C **1933** on both ports 1 and 2. LPAR **1938-6** and **1938-7** of load balancing IHS **1904** may access adapter **1929** to communicate via NETWORK C **1933**.

The hardware configuration information of adapter **1930** includes MSN of 0000FFA1, PID of 000B, LID of 0102, type of 0087, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **1930** is located in physical channel 000B in load balancing IHS **1904** and may be identified logically by load balancing IHS **1904** as 0102. Adapter **1930** is a physical OSA network adapter and couples to NETWORK C **1933** on both ports 1 and 2. LPAR **1938-6** and **1938-7** of load balancing IHS **1904** may access adapter **1930** to communicate via NETWORK C **1933**.

The hardware configuration information of adapter **1931** includes MSN of 0000FFA1, PID of 0115, LID of 04CE, type of 0008, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **1931** is located in physical channel 0115 in load balancing IHS **1904** and may be identified logically by load balancing IHS **1904** as 04CE. Adapter **1931** is a physical RNIC network adapter and couples to NETWORK C **1933** on both ports 1 and 2. LPAR **1938-6** and **1938-7** of load balancing IHS **1904** may access adapter **1931** to communicate via NETWORK C **1933**.

The hardware configuration information of adapter **1932** includes MSN of 0000FFA1, PID of 0116, LID of 04D1, type of 0008, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **1932** is located in physical channel 0116 in load balancing IHS **1904** and may be identified logically by load balancing IHS **1904** as 04D1. Adapter **1932** is a physical RNIC network adapter and couples to NETWORK C **1933** on both ports 1 and 2. LPAR **1938-6** and **1938-7** of load balancing IHS **1904** may access adapter **1932** to communicate via NETWORK C **1933**.

The hardware configuration information of adapter **1916** includes MSN of 00DDA254, PID of 0001, LID of 00A3, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **1916** is located in physical channel 0001 in administered IHS **1906** and may be identified logically by administered IHS **1906** as 00A3. Adapter **1916** is a physical OSA network adapter and couples to NETWORK A **1915** on both ports 1 and 2. Administered IHS **1906** may access adapter **1916** to communicate via NETWORK A **1915**.

The hardware configuration information of adapter **1917** includes MSN of 00DDA254, PID of 0003, LID of 00B1, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **1917** is located in physical channel 0003 in administered IHS **1906** and may be identified logically by administered IHS **1906** as 00B1. Adapter **1917** is a physical RNIC network adapter and couples to NETWORK A **1915** on both ports 1 and 2. Administered IHS **1906** may access adapter **1917** to communicate via NETWORK A **1915**.

The hardware configuration information of adapter **1918** includes MSN of 00DDA254, PID of 0002, LID of 00A4, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **1918** is

located in physical channel 0002 in administered IHS **1906** and may be identified logically by administered IHS **1906** as 00A4. Adapter **1918** is a physical OSA network adapter and couples to NETWORK A **1915** on both ports 1 and 2. Administered IHS **1906** may access adapter **1918** to communicate via NETWORK A **1915**.

The hardware configuration information of adapter **1919** includes MSN of 00DDA254, PID of 0004, LID of 00B2, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **1919** is located in physical channel 0004 in administered IHS **1906** and may be identified logically by administered IHS **1906** as 00B2. Adapter **1919** is a physical RNIC network adapter and couples to NETWORK A **1915** on both ports 1 and 2. Administered IHS **1906** may access adapter **1919** to communicate via NETWORK A **1915**.

The hardware configuration information of adapter **1925** includes MSN of FAF33922, PID of 0023, LID of 00F6, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **1925** is located in physical channel 0023 in administered IHS **1908** and may be identified logically by administered IHS **1908** as 00F6. Adapter **1925** is a physical OSA network adapter and couples to NETWORK B **1924** on both ports 1 and 2. Administered IHS **1908** may access adapter **1925** to communicate via NETWORK B **1924**.

The hardware configuration information of adapter **1926** includes MSN of FAF33922, PID of 0032, LID of 00FF, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **1926** is located in physical channel 0032 in administered IHS **1908** and may be identified logically by administered IHS **1908** as 00FF. Adapter **1926** is a physical RNIC network adapter and couples to NETWORK B **1924** on both ports 1 and 2. Administered IHS **1908** may access adapter **1926** to communicate via NETWORK B **1924**.

The hardware configuration information of adapter **1927** includes MSN of FAF33922, PID of 0024, LID of 00F7, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **1927** is located in physical channel 0024 in administered IHS **1908** and may be identified logically by administered IHS **1908** as 00F7. Adapter **1927** is a physical OSA network adapter and couples to NETWORK B **1924** on both ports 1 and 2. Administered IHS **1908** may access adapter **1927** to communicate via NETWORK B **1924**.

The hardware configuration information of adapter **1928** includes MSN of FAF33922, PID of 0033, LID of 0100, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **1928** is located in physical channel 0033 in administered IHS **1908** and may be identified logically by administered IHS **1908** as 0100. Adapter **1928** is a physical RNIC network adapter and couples to NETWORK B **1924** on both ports 1 and 2. Administered IHS **1908** may access adapter **1928** to communicate via NETWORK B **1924**.

The hardware configuration information of adapter **1934** includes MSN of 363B77A2, PID of 0011, LID of 00C2, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **1934** is located in physical channel 0011 in administered IHS **1910** and may be identified logically by administered IHS **1910** as 00C2. Adapter **1934** is a physical OSA network adapter and couples to NETWORK C **1933** on both ports 1 and 2. Administered IHS **1910** may access adapter **1934** to communicate via NETWORK C **1933**.

The hardware configuration information of adapter **1935** includes MSN of 363B77A2, PID of 0002, LID of 0D01, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **1935** is located in physical channel 0002 in administered IHS **1910** and may be identified logically by administered IHS **1910** as 0D01. Adapter **1935** is a physical RNIC network adapter and couples to NETWORK C **1933** on both ports 1 and 2. Administered IHS **1910** may access adapter **1935** to communicate via NETWORK C **1933**.

The hardware configuration information of adapter **1936** includes MSN of 363B77A2, PID of 0012, LID of 00C3, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **1936** is located in physical channel 0012 in administered IHS **1910** and may be identified logically by administered IHS **1910** as 00C3. Adapter **1936** is a physical OSA network adapter and couples to NETWORK C **1933** on both ports 1 and 2. Administered IHS **1910** may access adapter **1936** to communicate via NETWORK C **1933**.

The hardware configuration information of adapter **1937** includes MSN of 363B77A2, PID of 0003, LID of 0D02, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **1937** is located in physical channel 0003 in administered IHS **1910** and may be identified logically by administered IHS **1910** as 0D02. Adapter **1937** is a physical RNIC network adapter and couples to NETWORK C **1933** on both ports 1 and 2. Administered IHS **1910** may access adapter **1937** to communicate via NETWORK C **1933**.

FIG. 21 is a block diagram showing one embodiment of the disclosed load balancing system **2100** utilizing PNet IDs. Load balancing system **2100** may utilize network adapter **2101**, administrative network **2102** and network adapter **2103** to couple HCM IHS **500** to administered IHS **2104**. Administered IHS **2104** may also be referred to as load balancing IHS **2104**. Load balancing system **2100** may utilize network adapter **2101**, administrative network **2102** and network adapter **2105** to couple HCM IHS **500** to administered IHS **2106**. Load balancing system **2100** may utilize network adapter **2101**, administrative network **2102** and network adapter **2107** to couple HCM IHS **500** to administered IHS **2108**. Administered IHSs **2104**, **2106** and **2108** couple via administrative network **2102** to HCM IHS **500** to enable HCM IHS **500** to administer HCM database **2200** with HCM tool **600** to the administered IHSs.

Load balancing system **2100** may utilize network adapter **2109** and/or network adapter **2110** and/or network adapter **2111** and/or network adapter **2112** and/or network adapter **2113** and/or network adapter **2114** via NETWORK A **2115** via network adapter **2116** and/or network adapter **2117** and/or network adapter **2118** and/or network adapter **2119** to couple load balancing IHS **2104** to administered IHS **2106**. Load balancing system **2100** may utilize network adapter **2120** and/or network adapter **2121** and/or network adapter **2122** and/or network adapter **2123** and/or network adapter **2124** and/or network adapter **2125** via NETWORK B **2126** via network adapter **2127** and/or network adapter **2128** and/or network adapter **2129** and/or network adapter **2130** to couple load balancing IHS **2104** to administered IHS **2106**.

In one embodiment, network adapter **2101**, **2103**, **2105** and **2107** may be Ethernet (ETH) adapters. Network adapters **2109**, **2110**, **2113**, **2116**, **2118**, **2120**, **2122**, **2123**, **2127** and **2128** may be open system adapters (OSAs). Network adapters **2111**, **2112**, **2114**, **2117**, **2119**, **2121**, **2124**, **2125**, **2129** and **2130** may be remote direct memory access (RDMA) enabled network adapter controllers (RNICs). In one embodi-

ment, administrative network **2102**, NETWORK A **2115** and NETWORK B **2126** may provide local area network (LAN) communications and/or wide area network (WAN) communications and/or virtual LAN communications and/or intranet communications and/or Internet communications to structures that couple thereto.

Load balancing IHS **2104** may include a hypervisor (not shown) that may create logical partition (LPAR) **2131-1**, LPAR **2131-2**, LPAR **2131-3**, LPAR **2131-4** and LPAR **2131-5** in load balancing IHS **2104**. LPAR **2131-1**, LPAR **2131-2** and LPAR **2131-3** may include virtual network adapter **2132-1**, virtual network adapter **2132-2** and virtual network adapter **2132-3**, respectively. Virtual network adapter **2132-1**, virtual network adapter **2132-2** and virtual network adapter **2132-3** may couple to network adapter **2109**, network adapter **2110** and network adapter **2113** via a channel, i.e., a bus. LPAR **2131-4** and LPAR **2131-5** may include virtual network adapter **2132-4** and virtual network adapter **2132-5**, respectively. Virtual network adapter **2132-4** and virtual network adapter **2132-5** may couple to network adapter **2120**, network adapter **2121** and network adapter **2123** via a channel.

LPAR **2131-1**, LPAR **2131-2** and LPAR **2131-3** may include virtual network adapter **2133-1**, virtual network adapter **2133-2** and virtual network adapter **2133-3**, respectively. Virtual network adapter **2133-1**, virtual network adapter **2133-2** and virtual network adapter **2133-3** may couple to network adapter **2111**, network adapter **2112** and network adapter **2114** via a channel. LPAR **2131-4** and LPAR **2131-5** may include virtual network adapter **2133-4** and virtual network adapter **2133-5**, respectively. Virtual network adapter **2133-4** and virtual network adapter **2133-5** may couple to network adapter **2121**, network adapter **2124** and network adapter **2125** via a channel.

In one embodiment, administered IHS **2108** may be a load balancing IHS. Administered IHS **2108** may include a hypervisor (not shown) that may create LPAR **2134-1** and LPAR **2134-2**. LPAR **2134-1** and LPAR **2134-2** may include virtual network adapter **2135-1** and virtual network adapter **2135-2**, respectively. Virtual network adapter **2135-1** and virtual network adapter **2135-2** may couple to network adapter **2127** and network adapter **2128** via a channel. LPAR **2134-1** and LPAR **2134-2** may include virtual network adapter **2136-1** and virtual network adapter **2136-2**, respectively. Virtual network adapter **2136-1** and virtual network adapter **2136-2** may couple to network adapter **2129** and network adapter **2130** via a channel.

FIG. 22 depicts one embodiment of HCM database **2200** in the disclosed load balancing system **2100**. HCM tool **600** may store the hardware configuration information in HCM database **2200** on a per adapter basis. In one embodiment, for each network adapter in load balancing system **2100**, HCM tool **600** may store, from the leftmost column to the rightmost column, the machine serial number (MSN), physical identification (PID), logical identification (LID), adapter type, logical partition (LPAR) access list, physical network identification (PNet ID) network adapter.

As shown in HCM database **2200**, the hardware configuration information of adapter **2109** includes MSN of 0DC0FFB2, PID of 0001, LID of 00F1, type of 0087, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2109** is located in physical channel 0001 in load balancing IHS **2104** and may be identified logically by load balancing IHS **2104** as 00F1. Adapter **2109** is a physical OSA network adapter and couples to NETWORK A **2115** on both ports 1 and 2. LPAR **2131-1**, **2131-2**

and **2131-3** of load balancing IHS **2104** may access adapter **2109** to communicate via NETWORK A **2115**.

The hardware configuration information of adapter **2110** includes MSN of 0DC0FFB2, PID of 0002, LID of 00F5, type of 0087, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2110** is located in physical channel 0002 in load balancing IHS **2104** and may be identified logically by load balancing IHS **2104** as 00F5. Adapter **2110** is a physical OSA network adapter and couples to NETWORK A **2115** on both ports 1 and 2. LPAR **2131-1**, **2131-2** and **2131-3** of load balancing IHS **2104** may access adapter **2110** to communicate via NETWORK A **2115**.

The hardware configuration information of adapter **2111** includes MSN of 0DC0FFB2, PID of 0111, LID of 0FF1, type of 0008, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2111** is located in physical channel 0111 in load balancing IHS **2104** and may be identified logically by load balancing IHS **2104** as 0FF1. Adapter **2111** is a physical RNIC network adapter and couples to NETWORK A **2115** on both ports 1 and 2. LPAR **2131-1**, **2131-2** and **2131-3** of load balancing IHS **2104** may access adapter **2111** to communicate via NETWORK A **2115**.

The hardware configuration information of adapter **2112** includes MSN of 0DC0FFB2, PID of 0112, LID of 0FF5, type of 0008, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2112** is located in physical channel 0112 in load balancing IHS **2104** and may be identified logically by load balancing IHS **2104** as 0FF5. Adapter **2112** is a physical RNIC network adapter and couples to NETWORK A **2115** on both ports 1 and 2. LPAR **2131-1**, **2131-2** and **2131-3** of load balancing IHS **2104** may access adapter **2112** to communicate via NETWORK A **2115**.

The hardware configuration information of adapter **2113** includes MSN of 0DC0FFB2, PID of 0003, LID of 00F9, type of 0087, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2113** is located in physical channel 0003 in load balancing IHS **2104** and may be identified logically by load balancing IHS **2104** as 00F9. Adapter **2113** is a physical OSA network adapter and couples to NETWORK A **2115** on both ports 1 and 2. LPAR **2131-1**, **2131-2** and **2131-3** of load balancing IHS **2104** may access adapter **2113** to communicate via NETWORK A **2115**.

The hardware configuration information of adapter **2114** includes MSN of 0DC0FFB2, PID of 0113, LID of 0FF9, type of 0008, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2114** is located in physical channel 0113 in load balancing IHS **2104** and may be identified logically by load balancing IHS **2104** as 0FF9. Adapter **2114** is a physical RNIC network adapter and couples to NETWORK A **2115** on both ports 1 and 2. LPAR **2131-1**, **2131-2** and **2131-3** of load balancing IHS **2104** may access adapter **2114** to communicate via NETWORK A **2115**.

The hardware configuration information of adapter **2120** includes MSN of 0DC0FFB2, PID of 0004, LID of 00FD, type of 0087, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2120** is located in physical channel 0004 in load balancing IHS **2104** and may be identified logically by load balancing IHS **2104** as 00FD. Adapter **2120** is a physical OSA network adapter and couples to NETWORK B **2126** on both ports 1 and 2. LPAR **2131-4** and **2131-5** of load balancing IHS **2104** may access adapter **2120** to communicate via NETWORK B **2126**.

The hardware configuration information of adapter **2121** includes MSN of 0DC0FFB2, PID of 0114, LID of 0FFD, type of 0008, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2121** is located in physical channel 0114 in load balancing IHS **2104**

51

and may be identified logically by load balancing IHS **2104** as OFFD. Adapter **2121** is a physical RNIC network adapter and couples to NETWORK B **2126** on both ports 1 and 2. LPAR **2131-4** and **2131-5** of load balancing IHS **2104** may access adapter **2121** to communicate via NETWORK B **2126**.

The hardware configuration information of adapter **2122** includes MSN of 0DC0FFB2, PID of 0005, LID of 0100, type of 0087, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2122** is located in physical channel 0005 in load balancing IHS **2104** and may be identified logically by load balancing IHS **2104** as 0100. Adapter **2122** is a physical OSA network adapter and couples to NETWORK B **2126** on both ports 1 and 2. LPAR **2131-4** and **2131-5** of load balancing IHS **2104** may access adapter **2122** to communicate via NETWORK B **2126**.

The hardware configuration information of adapter **2123** includes MSN of 0DC0FFB2, PID of 0006, LID of 0103, type of 0087, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2123** is located in physical channel 0006 in load balancing IHS **2104** and may be identified logically by load balancing IHS **2104** as 0103. Adapter **2123** is a physical OSA network adapter and couples to NETWORK B **2126** on both ports 1 and 2. LPAR **2131-4** and **2131-5** of load balancing IHS **2104** may access adapter **2123** to communicate via NETWORK B **2126**.

The hardware configuration information of adapter **2124** includes MSN of 0DC0FFB2, PID of 0115, LID of 1000, type of 0008, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2124** is located in physical channel 0115 in load balancing IHS **2104** and may be identified logically by load balancing IHS **2104** as 1000. Adapter **2124** is a physical RNIC network adapter and couples to NETWORK B **2126** on both ports 1 and 2. LPAR **2131-4** and **2131-5** of load balancing IHS **2104** may access adapter **2124** to communicate via NETWORK B **2126**.

The hardware configuration information of adapter **2125** includes MSN of 0DC0FFB2, PID of 0116, LID of 1003, type of 0008, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2125** is located in physical channel 0116 in load balancing IHS **2104** and may be identified logically by load balancing IHS **2104** as 1003. Adapter **2125** is a physical RNIC network adapter and couples to NETWORK B **2126** on both ports 1 and 2. LPAR **2131-4** and **2131-5** of load balancing IHS **2104** may access adapter **2125** to communicate via NETWORK B **2126**.

The hardware configuration information of adapter **2116** includes MSN of 0000D100, PID of 0033, LID of 0D01, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2116** is located in physical channel 0033 in administered IHS **2106** and may be identified logically by administered IHS **2106** as 0D01. Adapter **2116** is a physical OSA network adapter and couples to NETWORK A **2115** on both ports 1 and 2. Administered IHS **2106** may access adapter **2116** to communicate via NETWORK A **2115**.

The hardware configuration information of adapter **2117** includes MSN of 0000D100, PID of 0025, LID of 0D03, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2117** is located in physical channel 0025 in administered IHS **2106** and may be identified logically by administered IHS **2106** as 0D03. Adapter **2117** is a physical RNIC network adapter and couples to NETWORK A **2115** on both ports 1 and 2. Administered IHS **2106** may access adapter **2117** to communicate via NETWORK A **2115**.

The hardware configuration information of adapter **2118** includes MSN of 0000D100, PID of 0034, LID of 0D02, type

52

of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2118** is located in physical channel 0034 in administered IHS **2106** and may be identified logically by administered IHS **2106** as 0D02.

5 Adapter **2118** is a physical OSA network adapter and couples to NETWORK A **2115** on both ports 1 and 2. Administered IHS **2106** may access adapter **2118** to communicate via NETWORK A **2115**.

The hardware configuration information of adapter **2119** includes MSN of 0000D100, PID of 0026, LID of 0D04, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2119** is located in physical channel 0026 in administered IHS **2106** and may be identified logically by administered IHS **2106** as 0D04. 10 Adapter **2119** is a physical RNIC network adapter and couples to NETWORK A **2115** on both ports 1 and 2. Administered IHS **2106** may access adapter **2119** to communicate via NETWORK A **2115**.

The hardware configuration information of adapter **2127** includes MSN of FFFFA200, PID of 0011, LID of 000A, type of 0087, LPAR access list of 01 and 02, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2127** is located in physical channel 0011 in load balancing IHS **2108** and may be identified logically by load balancing IHS **2108** as 000A. 20 Adapter **2127** is a physical OSA network adapter and couples to NETWORK B **2126** on both ports 1 and 2. LPAR **2134-1** and **2134-2** of load balancing IHS **2108** may access adapter **2127** to communicate via NETWORK B **2126**.

The hardware configuration information of adapter **2128** includes MSN of FFFFA200, PID of 0012, LID of 000B, type of 0087, LPAR access list of 01 and 02, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2128** is located in physical channel 0012 in load balancing IHS **2108** and may be identified logically by load balancing IHS **2108** as 000B. 30 Adapter **2128** is a physical OSA network adapter and couples to NETWORK B **2126** on both ports 1 and 2. LPAR **2134-1** and **2134-2** of load balancing IHS **2108** may access adapter **2128** to communicate via NETWORK B **2126**.

The hardware configuration information of adapter **2129** includes MSN of FFFFA200, PID of 0021, LID of 0F01, type of 0008, LPAR access list of 01 and 02, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2129** is located in physical channel 0021 in load balancing IHS **2108** and may be identified logically by load balancing IHS **2108** as 0F01. 40 Adapter **2129** is a physical RNIC network adapter and couples to NETWORK B **2126** on both ports 1 and 2. LPAR **2134-1** and **2134-2** of load balancing IHS **2108** may access adapter **2129** to communicate via NETWORK B **2126**.

The hardware configuration information of adapter **2130** includes MSN of FFFFA200, PID of 0022, LID of 0F02, type of 0008, LPAR access list of 01 and 02, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2130** is located in physical channel 0022 in load balancing IHS **2108** and may be identified logically by load balancing IHS **2108** as 0F02. 50 Adapter **2130** is a physical RNIC network adapter and couples to NETWORK B **2126** on both ports 1 and 2. LPAR **2134-1** and **2134-2** of load balancing IHS **2108** may access adapter **2130** to communicate via NETWORK B **2126**.

FIG. 23 is a block diagram of a load balancing information handling system (IHS) **2300** that may be used in the disclosed load balancing system. With respect to FIG. 11, like numbers indicate like elements. Load balancing IHS **2300** includes a processor **2305** that may include multiple cores. RNIC converging IHS **2300** processes, transfers, communicates, modifies, stores or otherwise handles information in digital form, analog form or other form. In one embodiment, load balancing IHS **2300** includes a bus **2310**, i.e. channel **2310**. In 65

another embodiment, bus **2310** may be multiple busses, i.e., multiple channels. Bus **2310** may couple processor **2305** to memory **2315** via a memory controller **2320** and memory bus **2325**. System memory **2315** may also be referred to as main memory. System memory **2315** may be a static random access memory (SRAM) array or a dynamic random access memory (DRAM) array. Processor **2305** may also include local memory such as L1, L2 and L3 caches.

In one embodiment, a video graphics controller **2330** couples display **2335** to bus **2310**. In another embodiment, load balancing IHS **2300** may operate without display **2335** and/or video graphics controller **2330**. Nonvolatile storage **2340**, such as a hard disk drive, solid-state drive (SSD), CD drive, DVD drive, or other nonvolatile storage couples to bus **2310** to provide load balancing IHS **2300** with permanent storage of information. System memory **2315** and nonvolatile storage **2340** are both forms of memory stores. In one embodiment, nonvolatile storage **2340** stores a hypervisor **2345** (HYPERVISOR) that governs operation of load balancing IHS **2300**. In another embodiment, nonvolatile storage **2340** may store an operating system (not shown) that governs operation of load balancing IHS **2300**. In another embodiment, nonvolatile storage **2340** may store an operating system (not shown) that governs operation of load balancing IHS **2300**, where the operating system includes a hypervisor (not shown).

I/O devices **2350**, such as speakers, a keyboard and a pointing device, may couple to bus **2310** via I/O controller **2355** and I/O bus **2360**. One or more expansion busses **2365**, i.e. channels **2365**, such as USB, IEEE 1394 bus, ATA, SATA, PCI, PCIE, DVI, HDMI and other busses, i.e. channels, couple to bus **2310** to facilitate the connection of peripherals and devices to load balancing IHS **2300**. Network interface controllers (NICs), for example, NIC **2370-1**, NIC **2370-2**, . . . , NIC **2370-J**, wherein J is the number of NICs, may couple to bus **2310** to enable load balancing IHS **2300** to connect by wire or wirelessly to a network and other information handling systems. NIC **2370-1**, NIC **2370-2**, . . . , NIC **2370-J** may also be called a network communication adapter, network interface adapter, network adapter, network interface or an adapter. NIC **2370-1**, NIC **2370-2**, . . . , NIC **2370-J** may take many forms. For example, NIC **2370-1**, NIC **2370-2**, . . . , NIC **2370-J** may take the form of an Ethernet (ETH) adapter, open systems adapter (OSA), RDMA enabled network interface controller (RNIC) or other network communication adapter.

While FIG. **23** shows one IHS that employs processor **2305**, the IHS may take many forms. For example, load balancing IHS **2300** may take the form of a mainframe, server, central processor complex (CPC), desktop, portable, laptop, notebook, tablet or other form factor computer or data processing system. Load balancing IHS **2300** may take other form factors such as a gaming device, a personal digital assistant (PDA), a portable telephone device, a communication device or other devices that include a processor and memory.

Load balancing IHS **2300** includes a load balancing tool computer program product **2400** on digital media **2375** such as a CD, DVD or other media. For simplicity, the term load balancing tool will be used below. Load balancing IHS **2300** may store load balancing tool **2400** in nonvolatile storage **2340** as load balancing tool **2400'**. Load balancing IHS **2300** may also store hypervisor **2345** (HYPERVISOR) and logical partition (LPAR) **2380-1**, LPAR **2380-2**, . . . , LPAR **2380-H**, wherein H is the number of LPARs, in nonvolatile storage **2340**.

In another embodiment, load balancing tool **2400'** may be part of the hypervisor **2345** (not shown). In another embodiment, load balancing tool **2400'** may be in LPAR **2380-1**, LPAR **2380-2**, . . . , LPAR **2380-H**. In another embodiment, load balancing IHS **2300** may store an operating system (not shown) that governs operation of load balancing IHS **2300**, where the operating system includes a hypervisor (not shown) and where the operating system includes LPAR **2380-1**, LPAR **2380-2**, . . . , LPAR **2380-H** as virtual machines (not shown). When load balancing IHS **2300** initializes, the IHS loads hypervisor **2345** into system memory **2315** for execution as hypervisor **2345'**. Load balancing IHS **2300** also loads load balancing tool **2400'** into system memory **2315** for execution as load balancing tool **2400''**. Load balancing IHS **2300** may also load LPAR **2380-1**, LPAR **2380-2**, . . . , LPAR **2380-H** into system memory **2315** for execution as LPAR **2380-1'**, LPAR **2380-2'**, . . . , LPAR **2380-H'**, respectively.

In another embodiment, when load balancing IHS **2300** initializes, the IHS may load an operating system (not shown) into system memory **2315** for execution. In another embodiment, when load balancing IHS **2300** initializes, the IHS may load an operating system (not shown) that includes a hypervisor (not shown) and includes LPAR **2380-1**, LPAR **2380-2**, . . . , LPAR **2380-H** as virtual machines (not shown) into system memory **2315** for execution.

FIG. **24** is a flowchart that shows a representative process flow of a load balancing tool **2400** that may be used in the disclosed load balancing system. Process flow commences when load balancing tool **2400** in load balancing IHS **2300** initializes, as per block **2405**. If HCM tool **600** in HCM IHS **500** does transmit HCM database **580**, as per decision block **2410**, a hypervisor agent in load balancing IHS **2300** may receive HCM database **580**, as per block **2415**. In one embodiment, the hypervisor agent in the load balancing IHS **2300** is included in hypervisor **2345**.

The hypervisor agent may allow hypervisor **2345** to access HCM database **580**. Hypervisor **2345** may transmit HCM database **580** to load balancing tool **2400**, as per block **2420**. Load balancing tool **2400** may extract the hardware configuration information of load balancing IHS **2300** from the HCM database **580**, as per block **2425**. In one embodiment, the hardware configuration information of load balancing IHS **2300** from HCM database **580** may include, but is not limited to, on a per adapter basis, machine serial numbers (MSNs), physical identifications (PIDs), logical identifications (LIDs), adapter types, a logical partition (LPAR) access list, a physical network identification (PNet ID) of the first port of the adapter and a PNet ID of the second port of the adapter. In one embodiment, the adapter type "0087" may be an OSA network adapter and the adapter type "0008" may be an RNIC network adapter.

In one embodiment, the load balancing tool **2400** may share the extracted hardware configuration information of load balancing IHS **2300** with hypervisor **2345**. Hypervisor **2345** may update the hardware configuration of load balancing IHS **2300** with the extracted hardware configuration information of load balancing IHS **2300**. In another embodiment, the load balancing tool **2400** may share the extracted hardware configuration information of load balancing IHS **2300** with LPARs **2380-1**, **2380-2**, . . . , **2380-H**, where H is the number of LPARs in load balancing IHS **2300**. LPARs **2380-1**, **2380-2**, . . . , **2380-H** may update their respective hardware configuration with the extracted hardware configuration information of load balancing IHS **2300**.

Load balancing tool **2400** may sort the extracted hardware configuration information by PNet IDs, as per block **2430**. For example, the load balancing tool **2400** may list all adapt-

ers with the PNet ID of “NETA” first, followed by all adapters with the PNet ID of “NETB”. Load balancing tool 2400 may further sort the extracted configuration information by adapter type, as per block 2435.

Load balancing tool 2400 may group adapters by adapter type on a PNet ID basis, as per block 2440. For example, the load balancing tool 2400 may group all adapters with the type “0087” and the PNet ID “NETA” first, followed by the adapters with the type “0008” and the PNet ID of “NETA”, further followed by the adapters with the type “0087” and the PNet ID of “NETB”. Referring back to decision block 2410, if HCM tool 600 in HCM IHS 500 does not transmit HCM database 580, as per block 2410, process flow continues at decision block 2445.

Load balancing tool 2400 may decide if the adapter loads on load balancing IHS 2300 are balanced, as per decision block 2445. If the adapter loads are not balanced, load balancing tool 2400 may balance the loads between like adapters with matching PNet IDs, as per block 2450. For example, OSA network adapter 1911 and OSA network adapter 1912 may both have a PNet ID of “NETA”. LPAR 1938-1, 1938-2, 1938-3 may access OSA network adapter 1911 and 1912. In one embodiment, LPAR 1938-1, 1938-2 and 1938-3 may be utilizing OSA network adapter 1911 for communication to NETWORK A 1915. Load balancing tool 2400 may balance the load of LPAR 1938-1, 1938-2 and 1938-3 through OSA network adapter 1911 by denying LPAR 1938-2 and LPAR 1938-3 access to OSA adapter 1911. In response, LPAR 1938-2 and LPAR 1938-3 may utilize OSA adapter 1912 for communication to NETWORK A 1915, thereby balancing the load between OSA network adapter 1911 and 1912. Process flow continues at block 2455.

If load balancing tool 2400 determines that the adapter load is in balance, as per decision block 2445, process flow continues at block 2455. Load balancing tool 2400 may decide if an adapter on load balancing IHS 2300 has failed, as per decision block 2455. If load balancing tool 2400 determines that an adapter has not failed, as per decision block 2455, process flow continues at decision block 2410. If load balancing tool 2400 determines that an adapter on load balancing IHS 2300 has failed, as per decision block 2455, load balancing tool 2400 may failover the adapter to a like adapter with matching PNet IDs, as per block 2460.

For example, OSA network adapter 1911 and OSA network adapter 1912 may both have a PNet ID of “NETA”. LPAR 1938-1, 1938-2, 1938-3 may access OSA network adapter 1911 and 1912. In one embodiment, LPAR 1938-1, 1938-2 and 1938-3 may be utilizing OSA network adapter 1911 for communication to NETWORK A 1915. Load balancing tool 2400 may determine that OSA adapter 1911 is experiencing failure. Load balancing tool 2400 may failover OSA adapter 1911 to OSA adapter 1912 by denying LPAR 1938-1, 1938-2 and 1938-3 access to network adapter 1911. In response, LPAR 1938-1, LPAR 1938-2 and LPAR 1938-3 may utilize OSA adapter 1912 for communication to NETWORK A 1915, thereby the communications utilizing OSA network adapter 1911 failover to OSA network adapter 1912. Process flow terminates at end block 2465. Alternatively, process flow may continue at start block 2405.

V. Privileged Network Access System

FIGS. 25A and 25B are block diagrams showing one embodiment of the disclosed privileged network access (PNA) system 2500 utilizing PNet IDs. PNA system 2500 may utilize network adapter 2501, administrative network 2502 and network adapter 2503 to couple HCM IHS 500 to administered IHS 2504. Administered IHS 2504 may also be referred to as PNA IHS 2504. PNA system 2500 may utilize

network adapter 2501, administrative network 2502 and network adapter 2505 to couple HCM IHS 500 to privileged network access management (PNAM) IHS 3200. PNA system 2500 may utilize network adapter 2501, administrative network 2502 and network adapter 2506 to couple HCM IHS 500 to administered IHS 2507. PNA system 2500 may utilize network adapter 2501, administrative network 2502 and network adapter 2508 to couple HCM IHS 500 to administered IHS 2509. PNA system 2500 may utilize network adapter 2501, administrative network 2502 and network adapter 2510 to couple HCM IHS 500 to administered IHS 2511. Administered IHSs 2504, 2507, 2509 and 2511 couple via administrative network 2502 to HCM IHS 500 to enable HCM IHS 500 to administer HCM database 2600 with HCM tool 600 to the administered IHSs. Administered IHSs 2504, 2507, 2509 and 2511 couple via administrative network 2502 to PNAM IHS 3200 to enable PNAM IHS 3200 to administer PNAM database 2700 with PNAM tool 3400 to the administered IHSs.

PNA system 2500 may utilize network adapter 2512 and/or network adapter 2513 via NETWORK A 2514 via network adapter 2515 and/or network adapter 2516 to couple PNA IHS 2504 to administered IHS 2507. PNA system 2500 may utilize network adapter 2517 and/or network adapter 2518 via NETWORK B 2519 via network adapter 2520 and/or network adapter 2521 to couple PNA IHS 2504 to administered IHS 2509. PNA system 2500 may utilize network adapter 2522 and/or network adapter 2523 via NETWORK C 2524 via network adapter 2525 and/or network adapter 2526 to couple PNA IHS 2504 to administered IHS 2509. PNA system 2500 may utilize network adapter 2522 and/or network adapter 2523 via NETWORK C 2524 via network adapter 2527 and/or network adapter 2528 to couple PNA IHS 2504 to administered IHS 2511.

In one embodiment, network adapters 2501, 2503, 2505, 2506, 2508 and 2510 may be Ethernet (ETH) adapters. Network adapters 2512, 2515, 2517, 2520, 2522, 2525 and 2527 may be open system adapters (OSAs). Network adapters 2513, 2516, 2518, 2521, 2523, 2526 and 2528 may be remote direct memory access (RDMA) enabled network adapter controllers (RNICs). In one embodiment, administrative network 2502, NETWORK A 2514, NETWORK B 2519 and NETWORK C 2524 may provide local area network (LAN) communications and/or wide area network (WAN) communications and/or virtual LAN communications and/or intranet communications and/or Internet communications to structures that couple thereto.

PNA IHS 2504 may include a hypervisor (not shown) that may create logical partition (LPAR) 2529-1, LPAR 2529-2, LPAR 2529-3, LPAR 2529-4, LPAR 2529-5, LPAR 2529-6 and LPAR 2529-7 in PNA IHS 2504. LPAR 2529-1, LPAR 2529-2 and LPAR 2529-3 may include virtual network adapter 2530-1, virtual network adapter 2530-2 and virtual network adapter 2530-3, respectively. Virtual network adapter 2530-1, virtual network adapter 2530-2 and virtual network adapter 2530-3 may couple to network adapter 2512 via a channel, i.e., a bus. LPAR 2529-4 and LPAR 2529-5 may include virtual network adapter 2530-4 and virtual network adapter 2530-5, respectively. Virtual network adapter 2530-4 and virtual network adapter 2530-5 may couple to network adapter 2517 via a channel. LPAR 2529-6 and LPAR 2529-7 may include virtual network adapter 2530-6 and virtual network adapter 2530-7, respectively. Virtual network adapter 2530-6 and virtual network adapter 2530-7 may couple to network adapter 2522 via a channel.

LPAR 2529-1, LPAR 2529-2 and LPAR 2529-3 may include virtual network adapter 2531-1, virtual network

adapter **2531-2** and virtual network adapter **2531-3**, respectively. Virtual network adapter **2531-1**, virtual network adapter **2531-2** and virtual network adapter **2531-3** may couple to network adapter **2513** via a channel. LPAR **2529-4** and LPAR **2529-5** may include virtual network adapter **2531-4** and virtual network adapter **2531-5**, respectively. Virtual network adapter **2531-4** and virtual network adapter **2531-5** may couple to network adapter **2518** via a channel. LPAR **2529-6** and LPAR **2529-7** may include virtual network adapter **2531-6** and virtual network adapter **2531-7**, respectively. Virtual network adapter **2531-6** and virtual network adapter **2531-7** may couple to network adapter **2523** via a channel.

FIG. 26 depicts one embodiment of HCM database **2600** in the disclosed privileged network access (PNA) system **2500**. HCM tool **600** may store the hardware configuration information in HCM database **2600** on a per adapter basis. In one embodiment, for each network adapter in PNA system **2500**, HCM tool **600** may store, from the leftmost column to the rightmost column, the machine serial number (MSN), physical identification (PID), logical identification (LID), adapter type, logical partition (LPAR) access list, physical network identification (PNet ID) network adapter.

As shown in HCM database **2600**, the hardware configuration information of adapter **2512** includes MSN of 0CCCC0AB2, PID of 0001, LID of 00F1, type of 0087, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2512** is located in physical channel 0001 in PNA IHS **2504** and may be identified logically by PNA IHS **2504** as 00F1. Adapter **2512** is a physical OSA network adapter and couples to NETWORK A **2514** on both ports 1 and 2. LPAR **2529-1**, **2529-2** and **2529-3** of PNA IHS **2504** may access adapter **2512** to communicate via NETWORK A **2514**.

The hardware configuration information of adapter **2513** includes MSN of 0CCCC0AB2, PID of 0111, LID of 00A1, type of 0008, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2513** is located in physical channel 0111 in PNA IHS **2504** and may be identified logically by PNA IHS **2504** as 00A1. Adapter **2513** is a physical RNIC network adapter and couples to NETWORK A **2514** on both ports 1 and 2. LPAR **2529-1**, **2529-2** and **2529-3** of PNA IHS **2504** may access adapter **2513** to communicate via NETWORK A **2514**.

The hardware configuration information of adapter **2517** includes MSN of 0CCCC0AB2, PID of 0002, LID of 00F5, type of 0087, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2517** is located in physical channel 0002 in PNA IHS **2504** and may be identified logically by PNA IHS **2504** as 00F5. Adapter **2517** is a physical OSA network adapter and couples to NETWORK B **2519** on both ports 1 and 2. LPAR **2529-4** and **2529-5** of PNA IHS **2504** may access adapter **2517** to communicate via NETWORK B **2519**.

The hardware configuration information of adapter **2518** includes MSN of 0CCCC0AB2, PID of 0112, LID of 00A5, type of 0008, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2518** is located in physical channel 0112 in PNA IHS **2504** and may be identified logically by PNA IHS **2504** as 00A5. Adapter **2518** is a physical RNIC network adapter and couples to NETWORK B **2519** on both ports 1 and 2. LPAR **2529-4** and **2529-5** of PNA IHS **2504** may access adapter **2518** to communicate via NETWORK B **2519**.

The hardware configuration information of adapter **2522** includes MSN of 0CCCC0AB2, PID of 0003, LID of 00F8, type of 0087, LPAR access list of 06 and 07, and PNet ID 1

and PNet ID 2 of NETC. In other words, adapter **2522** is located in physical channel 0003 in PNA IHS **2504** and may be identified logically by PNA IHS **2504** as 00F8. Adapter **2522** is a physical OSA network adapter and couples to NETWORK C **2524** on both ports 1 and 2. LPAR **2529-6** and **2529-7** of PNA IHS **2504** may access adapter **2522** to communicate via NETWORK C **2524**.

The hardware configuration information of adapter **2523** includes MSN of 0CCCC0AB2, PID of 0113, LID of 00A8, type of 0008, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **2523** is located in physical channel 0113 in PNA IHS **2504** and may be identified logically by PNA IHS **2504** as 00A8. Adapter **2523** is a physical RNIC network adapter and couples to NETWORK C **2524** on both ports 1 and 2. LPAR **2529-6** and **2529-7** of PNA IHS **2504** may access adapter **2523** to communicate via NETWORK C **2524**.

The hardware configuration information of adapter **2515** includes MSN of DFA22601, PID of 0001, LID of 00F4, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2515** is located in physical channel 0001 in administered IHS **2507** and may be identified logically by administered IHS **2507** as 00F4. Adapter **2515** is a physical OSA network adapter and couples to NETWORK A **2514** on both ports 1 and 2. Administered IHS **2507** may access adapter **2515** to communicate via NETWORK A **2514**.

The hardware configuration information of adapter **2516** includes MSN of DFA22601, PID of 0002, LID of 00A4, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2516** is located in physical channel 0002 in administered IHS **2507** and may be identified logically by administered IHS **2507** as 00A4. Adapter **2516** is a physical RNIC network adapter and couples to NETWORK A **2514** on both ports 1 and 2. Administered IHS **2507** may access adapter **2516** to communicate via NETWORK A **2514**.

The hardware configuration information of adapter **2520** includes MSN of 33300FB8, PID of 0001, LID of 00F5, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2520** is located in physical channel 0001 in administered IHS **2509** and may be identified logically by administered IHS **2509** as 00F5. Adapter **2520** is a physical OSA network adapter and couples to NETWORK B **2519** on both ports 1 and 2. Administered IHS **2509** may access adapter **2520** to communicate via NETWORK B **2519**.

The hardware configuration information of adapter **2521** includes MSN of 33300FB8, PID of 0011, LID of 00F6, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2521** is located in physical channel 0011 in administered IHS **2509** and may be identified logically by administered IHS **2509** as 00F6. Adapter **2521** is a physical RNIC network adapter and couples to NETWORK B **2519** on both ports 1 and 2. Administered IHS **2509** may access adapter **2521** to communicate via NETWORK B **2519**.

The hardware configuration information of adapter **2525** includes MSN of 33300FB8, PID of 0002, LID of 00A5, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **2525** is located in physical channel 0002 in administered IHS **2509** and may be identified logically by administered IHS **2509** as 00A5. Adapter **2525** is a physical OSA network adapter and couples to NETWORK C **2524** on both ports 1 and 2. Administered IHS **2509** may access adapter **2525** to communicate via NETWORK C **2524**.

The hardware configuration information of adapter **2526** includes MSN of 33300FB8, PID of 0012, LID of 00A6, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **2526** is located in physical channel 0012 in administered IHS **2509** and may be identified logically by administered IHS **2509** as 00A6. Adapter **2526** is a physical RNIC network adapter and couples to NETWORK C **2524** on both ports 1 and 2. Administered IHS **2509** may access adapter **2526** to communicate via NETWORK C **2524**.

The hardware configuration information of adapter **2527** includes MSN of 0000FC32, PID of 0031, LID of 0D01, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **2527** is located in physical channel 0031 in administered IHS **2511** and may be identified logically by administered IHS **2511** as 0D01. Adapter **2527** is a physical OSA network adapter and couples to NETWORK C **2524** on both ports 1 and 2. Administered IHS **2511** may access adapter **2527** to communicate via NETWORK C **2524**.

The hardware configuration information of adapter **2528** includes MSN of 0000FC32, PID of 0033, LID of 0D03, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **2528** is located in physical channel 0033 in administered IHS **2511** and may be identified logically by administered IHS **2511** as 0D03. Adapter **2528** is a physical RNIC network adapter and couples to NETWORK C **2524** on both ports 1 and 2. Administered IHS **2511** may access adapter **2528** to communicate via NETWORK C **2524**.

FIG. 27 depicts one embodiment of privileged network access management (PNAM) database **2700** in the disclosed PNA system **2500**. PNAM tool **3400** may store the privileged network access information in PNAM database **2700** on a per PNet ID, per IHS basis. In one embodiment, for each network adapter in PNA system **2500**, PNAM tool **3400** may store, from the leftmost column to the rightmost column, the physical network identification (PNet ID), the machine serial number (MSN) and the logical partition (LPAR) access list.

As shown in PNAM database **2700**, the privileged network access information in the first row of PNAM database **2700** may include a PNet ID of NETB, MSN of 0CCCC0AB2 and LPAR access list of 04 and 05. In other words, NETWORK B **2519** is a privileged network. A PNA tool **3300** may grant LPARs **2529-4** and **2529-5** in PNA IHS **2504** access to privileged NETWORK B **2519**.

The privileged network access information in the second row of PNAM database **2700** may include a PNet ID of NETB, MSN of 33300FB8 and LPAR access list with no entries. In other words, NETWORK B **2519** is a privileged network. In one embodiment, a PNA tool **3300** may grant administered IHS **2509** access to privileged NETWORK B **2519**.

The privileged network access information in the third row of PNAM database **2700** may include a PNet ID of NETC, MSN of 0CCCC0AB2 and LPAR access list of 07. In other words, NETWORK C **2524** is a privileged network. A PNA tool **3300** may grant LPAR **2529-7** in PNA IHS **2504** access to privileged NETWORK C **2524**. A PNA tool **3300** may deny LPAR **2529-6** in PNA IHS **2504** access to privileged NETWORK C **2524**, even though LPAR **2529-6** is coupled to NETWORK C **2524** via network adapters **2522** and **2523**.

The privileged network access information in the fourth row of PNAM database **2700** may include a PNet ID of NETC, MSN of 33300FB8 and LPAR access list with no entries. In other words, NETWORK C **2524** is a privileged

network. In one embodiment, a PNA tool **3300** may grant administered IHS **2509** access to privileged NETWORK C **2524**.

The privileged network access information in the fifth row of PNAM database **2700** may include a PNet ID of NETC, MSN of 0000FC32 and LPAR access list with no entries. In other words, NETWORK C **2524** is a privileged network. In one embodiment, a PNA tool **3300** may grant administered IHS **2511** access to privileged NETWORK C **2524**.

FIGS. 28A and 28B are block diagrams showing one embodiment of the disclosed PNA system **2800** utilizing PNet IDs. PNA system **2800** may utilize network adapter **2801**, administrative network **2802** and network adapter **2803** to couple HCM IHS **500** to administered IHS **2804**. Administered IHS **2804** may also be referred to as PNA IHS **2804**. PNA system **2800** may utilize network adapter **2801**, administrative network **2802** and network adapter **2805** to couple HCM IHS **500** to privileged network access management (PNAM) IHS **3200**. PNA system **2800** may utilize network adapter **2801**, administrative network **2802** and network adapter **2806** to couple HCM IHS **500** to administered IHS **2807**. PNA system **2800** may utilize network adapter **2801**, administrative network **2802** and network adapter **2808** to couple HCM IHS **500** to administered IHS **2809**. PNA system **2800** may utilize network adapter **2801**, administrative network **2802** and network adapter **2810** to couple HCM IHS **500** to administered IHS **2811**. Administered IHSs **2804**, **2807**, **2809** and **2811** couple via administrative network **2802** to HCM IHS **500** to enable HCM IHS **500** to administer HCM database **2900** with HCM tool **600** to the administered IHSs. Administered IHSs **2804**, **2807**, **2809** and **2811** couple via administrative network **2802** to PNAM IHS **3200** to enable PNAM IHS **3200** to administer PNAM database **3000** with PNAM tool **3400** to the administered IHSs.

PNA system **2800** may utilize network adapter **2812** and/or network adapter **2813** and/or network adapter **2814** and/or network adapter **2815** via NETWORK A **2816** via network adapter **2817** and/or network adapter **2818** to couple PNA IHS **2804** to administered IHS **2807**. PNA system **2800** may utilize network adapter **2819** and/or network adapter **2820** and/or network adapter **2821** and/or network adapter **2822** via NETWORK B **2823** via network adapter **2824** and/or network adapter **2825** to couple PNA IHS **2804** to administered IHS **2807**. PNA system **2800** may utilize network adapter **2819** and/or network adapter **2820** and/or network adapter **2821** and/or network adapter **2822** via NETWORK B **2823** via network adapter **2826** and/or network adapter **2827** and/or network adapter **2828** and/or network adapter **2829** to couple PNA IHS **2804** to administered IHS **2809**. PNA system **2800** may utilize network adapter **2830** and/or network adapter **2831** and/or network adapter **2832** and/or network adapter **2833** via NETWORK C **2834** via network adapter **2835** and/or network adapter **2836** and/or network adapter **2837** and/or network adapter **2838** to couple PNA IHS **2804** to administered IHS **2811**.

In one embodiment, network adapters **2801**, **2803**, **2805**, **2806**, **2808** and **2810** may be Ethernet (ETH) adapters. Network adapters **2812**, **2813**, **2817**, **2819**, **2820**, **2824**, **2826**, **2828**, **2830**, **2831**, **2835** and **2836** may be open system adapters (OSAs). Network adapters **2814**, **2815**, **2818**, **2821**, **2822**, **2824**, **2827**, **2829**, **2832**, **2833**, **2837** and **2838** may be remote direct memory access (RDMA) enabled network adapter controllers (RNICs). In one embodiment, administrative network **2802**, NETWORK A **2816**, NETWORK B **2823** and NETWORK C **2834** may provide local area network (LAN) communications and/or wide area network (WAN) communica-

tions and/or virtual LAN communications and/or intranet communications and/or Internet communications to structures that couple thereto.

PNA IHS **2804** may include a hypervisor (not shown) that may create logical partition (LPAR) **2839-1**, LPAR **2839-2**, LPAR **2839-3**, LPAR **2839-4**, LPAR **2839-5**, LPAR **2839-6** and LPAR **2839-7** in PNA IHS **2804**. LPAR **2839-1**, LPAR **2839-2** and LPAR **2839-3** may include virtual network adapter **2840-1**, virtual network adapter **2840-2** and virtual network adapter **2840-3**, respectively. Virtual network adapter **2840-1**, virtual network adapter **2840-2** and virtual network adapter **2840-3** may couple to network adapter **2812** and network adapter **2813** via a channel, i.e., a bus. LPAR **2839-4** and LPAR **2839-5** may include virtual network adapter **2840-4** and virtual network adapter **2840-5**, respectively. Virtual network adapter **2840-4** and virtual network adapter **2840-5** may couple to network adapter **2819** and network adapter **2820** via a channel. LPAR **2839-6** and LPAR **2839-7** may include virtual network adapter **2840-6** and virtual network adapter **2840-7**, respectively. Virtual network adapter **2840-6** and virtual network adapter **2840-7** may couple to network adapter **2830** and network adapter **2831** via a channel.

LPAR **2839-1**, LPAR **2839-2** and LPAR **2839-3** may include virtual network adapter **2841-1**, virtual network adapter **2841-2** and virtual network adapter **2841-3**, respectively. Virtual network adapter **2841-1**, virtual network adapter **2841-2** and virtual network adapter **2841-3** may couple to network adapter **2814** and network adapter **2815** via a channel. LPAR **2839-4** and LPAR **2839-5** may include virtual network adapter **2841-4** and virtual network adapter **2841-5**, respectively. Virtual network adapter **2841-4** and virtual network adapter **2841-5** may couple to network adapter **2821** and network adapter **2822** via a channel. LPAR **2839-6** and LPAR **2839-7** may include virtual network adapter **2841-6** and virtual network adapter **2841-7**, respectively. Virtual network adapter **2841-6** and virtual network adapter **2841-7** may couple to network adapter **2832** and network adapter **2833** via a channel.

In one embodiment, administered IHS **2811** may be a PNA IHS. Administered IHS **2811** may include a hypervisor (not shown) that may create LPAR **2842-1** and LPAR **2842-2**. LPAR **2842-1** and LPAR **2842-2** may include virtual network adapter **2843-1** and virtual network adapter **2843-2**, respectively. Virtual network adapter **2843-1** and virtual network adapter **2843-2** may couple to network adapter **2835** and network adapter **2836** via a channel. LPAR **2842-1** and LPAR **2842-2** may include virtual network adapter **2844-1** and virtual network adapter **2844-2**, respectively. Virtual network adapter **2844-1** and virtual network adapter **2844-2** may couple to network adapter **2837** and network adapter **2838** via a channel.

FIG. **29** depicts one embodiment of HCM database **2900** in the disclosed privileged network access (PNA) system **2800**. HCM tool **600** may store the hardware configuration information in HCM database **2900** on a per adapter basis. In one embodiment, for each network adapter in PNA system **2800**, HCM tool **600** may store, from the leftmost column to the rightmost column, the machine serial number (MSN), physical identification (PID), logical identification (LID), adapter type, logical partition (LPAR) access list, physical network identification (PNet ID) network adapter.

As shown in HCM database **2900**, the hardware configuration information of adapter **2812** includes MSN of 000AFA11, PID of 0001, LID of 00F1, type of 0087, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2812** is located in physical

channel 0001 in PNA IHS **2804** and may be identified logically by PNA IHS **2804** as 00F1. Adapter **2812** is a physical OSA network adapter and couples to NETWORK A **2816** on both ports 1 and 2. LPAR **2839-1**, **2839-2** and **2839-3** of PNA IHS **2804** may access adapter **2812** to communicate via NETWORK A **2816**.

The hardware configuration information of adapter **2813** includes MSN of 000AFA11, PID of 0002, LID of 00F5, type of 0087, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2813** is located in physical channel 0002 in PNA IHS **2804** and may be identified logically by PNA IHS **2804** as 00F5. Adapter **2813** is a physical OSA network adapter and couples to NETWORK A **2816** on both ports 1 and 2. LPAR **2839-1**, **2839-2** and **2839-3** of PNA IHS **2804** may access adapter **2813** to communicate via NETWORK A **2816**.

The hardware configuration information of adapter **2814** includes MSN of 000AFA11, PID of 0011, LID of 00A1, type of 0008, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2814** is located in physical channel 0011 in PNA IHS **2804** and may be identified logically by PNA IHS **2804** as 00A1. Adapter **2814** is a physical RNIC network adapter and couples to NETWORK A **2816** on both ports 1 and 2. LPAR **2839-1**, **2839-2** and **2839-3** of PNA IHS **2804** may access adapter **2814** to communicate via NETWORK A **2816**.

The hardware configuration information of adapter **2815** includes MSN of 000AFA11, PID of 0012, LID of 00A5, type of 0008, LPAR access list of 01, 02 and 03, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2815** is located in physical channel 0012 in PNA IHS **2804** and may be identified logically by PNA IHS **2804** as 00A5. Adapter **2815** is a physical RNIC network adapter and couples to NETWORK A **2816** on both ports 1 and 2. LPAR **2839-1**, **2839-2** and **2839-3** of PNA IHS **2804** may access adapter **2815** to communicate via NETWORK A **2816**.

The hardware configuration information of adapter **2819** includes MSN of 000AFA11, PID of 0003, LID of 00F9, type of 0087, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2819** is located in physical channel 0003 in PNA IHS **2804** and may be identified logically by PNA IHS **2804** as 00F9. Adapter **2819** is a physical OSA network adapter and couples to NETWORK B **2823** on both ports 1 and 2. LPAR **2839-4** and **2839-5** of PNA IHS **2804** may access adapter **2819** to communicate via NETWORK B **2823**.

The hardware configuration information of adapter **2820** includes MSN of 000AFA11, PID of 0004, LID of 00FC, type of 0087, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2820** is located in physical channel 0004 in PNA IHS **2804** and may be identified logically by PNA IHS **2804** as 00FC. Adapter **2820** is a physical OSA network adapter and couples to NETWORK B **2823** on both ports 1 and 2. LPAR **2839-4** and **2839-5** of PNA IHS **2804** may access adapter **2820** to communicate via NETWORK B **2823**.

The hardware configuration information of adapter **2821** includes MSN of 000AFA11, PID of 0013, LID of 00A9, type of 0008, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2821** is located in physical channel 0013 in PNA IHS **2804** and may be identified logically by PNA IHS **2804** as 00A9. Adapter **2821** is a physical RNIC network adapter and couples to NETWORK B **2823** on both ports 1 and 2. LPAR **2839-4** and **2839-5** of PNA IHS **2804** may access adapter **2821** to communicate via NETWORK B **2823**.

The hardware configuration information of adapter **2822** includes MSN of 000AFA11, PID of 0014, LID of 00AC, type of 0008, LPAR access list of 04 and 05, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2822** is located in physical channel 0014 in PNA IHS **2804** and may be identified logically by PNA IHS **2804** as 00AC. Adapter **2822** is a physical RNIC network adapter and couples to NETWORK B **2823** on both ports 1 and 2. LPAR **2839-4** and **2839-5** of PNA IHS **2804** may access adapter **2822** to communicate via NETWORK B **2823**.

The hardware configuration information of adapter **2830** includes MSN of 000AFA11, PID of 0005, LID of 00FF, type of 0087, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **2830** is located in physical channel 0005 in PNA IHS **2804** and may be identified logically by PNA IHS **2804** as 00FF. Adapter **2830** is a physical OSA network adapter and couples to NETWORK C **2834** on both ports 1 and 2. LPAR **2839-6** and **2839-7** of PNA IHS **2804** may access adapter **2830** to communicate via NETWORK C **2834**.

The hardware configuration information of adapter **2831** includes MSN of 000AFA11, PID of 0006, LID of 0102, type of 0087, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **2831** is located in physical channel 0006 in PNA IHS **2804** and may be identified logically by PNA IHS **2804** as 0102. Adapter **2831** is a physical OSA network adapter and couples to NETWORK C **2834** on both ports 1 and 2. LPAR **2839-6** and **2839-7** of PNA IHS **2804** may access adapter **2831** to communicate via NETWORK C **2834**.

The hardware configuration information of adapter **2832** includes MSN of 000AFA11, PID of 0015, LID of 00AF, type of 0008, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **2832** is located in physical channel 0015 in PNA IHS **2804** and may be identified logically by PNA IHS **2804** as 00AF. Adapter **2832** is a physical RNIC network adapter and couples to NETWORK C **2834** on both ports 1 and 2. LPAR **2839-6** and **2839-7** of PNA IHS **2804** may access adapter **2832** to communicate via NETWORK C **2834**.

The hardware configuration information of adapter **2833** includes MSN of 000B2A11, PID of 0016, LID of 00B2, type of 0008, LPAR access list of 06 and 07, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **2833** is located in physical channel 0016 in PNA IHS **2804** and may be identified logically by PNA IHS **2804** as 00B2. Adapter **2833** is a physical RNIC network adapter and couples to NETWORK C **2834** on both ports 1 and 2. LPAR **2839-6** and **2839-7** of PNA IHS **2804** may access adapter **2833** to communicate via NETWORK C **2834**.

The hardware configuration information of adapter **2817** includes MSN of 0000FC32, PID of 0001, LID of 0D01, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2817** is located in physical channel 0001 in administered IHS **2807** and may be identified logically by administered IHS **2807** as 0D01. Adapter **2817** is a physical OSA network adapter and couples to NETWORK A **2816** on both ports 1 and 2. Administered IHS **2807** may access adapter **2817** to communicate via NETWORK A **2816**.

The hardware configuration information of adapter **2818** includes MSN of 0000FC32, PID of 0021, LID of 0D03, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETA. In other words, adapter **2818** is located in physical channel 0021 in administered IHS **2807** and may be identified logically by administered IHS **2807** as 0D03. Adapter **2818** is a physical RNIC network adapter and

couples to NETWORK A **2816** on both ports 1 and 2. Administered IHS **2807** may access adapter **2818** to communicate via NETWORK A **2816**.

The hardware configuration information of adapter **2824** includes MSN of 0000FC32, PID of 0002, LID of 0D02, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2824** is located in physical channel 0002 in administered IHS **2807** and may be identified logically by administered IHS **2807** as 0D02. Adapter **2824** is a physical OSA network adapter and couples to NETWORK B **2823** on both ports 1 and 2. Administered IHS **2807** may access adapter **2824** to communicate via NETWORK B **2823**.

The hardware configuration information of adapter **2825** includes MSN of 0000FC32, PID of 0022, LID of 0D04, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2825** is located in physical channel 0022 in administered IHS **2807** and may be identified logically by administered IHS **2807** as 0D04. Adapter **2825** is a physical RNIC network adapter and couples to NETWORK B **2823** on both ports 1 and 2. Administered IHS **2807** may access adapter **2825** to communicate via NETWORK B **2823**.

The hardware configuration information of adapter **2826** includes MSN of DDDD00AB, PID of 0001, LID of 0001, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2826** is located in physical channel 0001 in administered IHS **2809** and may be identified logically by administered IHS **2809** as 0001. Adapter **2826** is a physical OSA network adapter and couples to NETWORK B **2823** on both ports 1 and 2. Administered IHS **2809** may access adapter **2826** to communicate via NETWORK B **2823**.

The hardware configuration information of adapter **2827** includes MSN of DDDD00AB, PID of 0011, LID of 0003, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2827** is located in physical channel 0011 in administered IHS **2809** and may be identified logically by administered IHS **2809** as 0003. Adapter **2827** is a physical RNIC network adapter and couples to NETWORK B **2823** on both ports 1 and 2. Administered IHS **2809** may access adapter **2827** to communicate via NETWORK B **2823**.

The hardware configuration information of adapter **2828** includes MSN of DDDD00AB, PID of 0002, LID of 0002, type of 0087, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2828** is located in physical channel 0002 in administered IHS **2809** and may be identified logically by administered IHS **2809** as 0002. Adapter **2828** is a physical OSA network adapter and couples to NETWORK B **2823** on both ports 1 and 2. Administered IHS **2809** may access adapter **2828** to communicate via NETWORK B **2823**.

The hardware configuration information of adapter **2829** includes MSN of DDDD00AB, PID of 0022, LID of 0004, type of 0008, LPAR access list with no entries, and PNet ID 1 and PNet ID 2 of NETB. In other words, adapter **2829** is located in physical channel 0022 in administered IHS **2809** and may be identified logically by administered IHS **2809** as 0004. Adapter **2829** is a physical RNIC network adapter and couples to NETWORK B **2823** on both ports 1 and 2. Administered IHS **2809** may access adapter **2829** to communicate via NETWORK B **2823**.

The hardware configuration information of adapter **2835** includes MSN of ACA000F1, PID of 0001, LID of 0081, type of 0087, LPAR access list of 01 and 02, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **2835** is located

in physical channel 0001 in PNA IHS **2811** and may be identified logically by PNA IHS **2811** as 0061. Adapter **2835** is a physical OSA network adapter and couples to NETWORK C **2834** on both ports 1 and 2. LPAR **2842-1** and **2842-2** of PNA IHS **2811** may access adapter **2835** to communicate via NETWORK C **2834**.

The hardware configuration information of adapter **2836** includes MSN of ACA000F1, PID of 0002, LID of 00B4, type of 0087, LPAR access list of 01 and 02, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **2836** is located in physical channel 0002 in PNA IHS **2811** and may be identified logically by PNA IHS **2811** as 00B4. Adapter **2836** is a physical OSA network adapter and couples to NETWORK C **2834** on both ports 1 and 2. LPAR **2842-1** and **2842-2** of PNA IHS **2811** may access adapter **2836** to communicate via NETWORK C **2834**.

The hardware configuration information of adapter **2837** includes MSN of ACA000F1, PID of 0021, LID of 00C1, type of 0008, LPAR access list of 01 and 02, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **2837** is located in physical channel 0021 in PNA IHS **2811** and may be identified logically by PNA IHS **2811** as 00C1. Adapter **2837** is a physical RNIC network adapter and couples to NETWORK C **2834** on both ports 1 and 2. LPAR **2842-1** and **2842-2** of PNA IHS **2811** may access adapter **2837** to communicate via NETWORK C **2834**.

The hardware configuration information of adapter **2838** includes MSN of ACA000F1, PID of 0022, LID of 00C4, type of 0008, LPAR access list of 01 and 02, and PNet ID 1 and PNet ID 2 of NETC. In other words, adapter **2838** is located in physical channel 0022 in PNA IHS **2811** and may be identified logically by PNA IHS **2811** as 00C4. Adapter **2838** is a physical RNIC network adapter and couples to NETWORK C **2834** on both ports 1 and 2. LPAR **2842-1** and **2842-2** of PNA IHS **2811** may access adapter **2838** to communicate via NETWORK C **2834**.

FIG. 30 depicts one embodiment of privileged network access management (PNAM) database **3000** in the disclosed PNA system **2800**. PNAM tool **3400** may store the privileged network access information in PNAM database **2900** on a per PNet ID, per IHS basis. In one embodiment, for each network adapter in PNA system **2800**, PNAM tool **3400** may store, from the leftmost column to the rightmost column, the physical network identification (PNet ID), the machine serial number (MSN) and the logical partition (LPAR) access list.

As shown in PNAM database **3000**, the privileged network access information in the first row of PNAM database **3000** may include a PNet ID of NETB, MSN of 000AFA11 and LPAR access list of 04 and 05. In other words, NETWORK B **2823** is a privileged network. PNA tool **3300** may grant LPARs **2839-4** and **2839-5** in PNA IHS **2804** access to privileged NETWORK B **2823**.

The privileged network access information in the second row of PNAM database **3000** may include a PNet ID of NETB, MSN of 0000FC32 and LPAR access list with no entries. In other words, NETWORK B **2823** is a privileged network. In one embodiment, PNA tool **3300** may grant administered IHS **2807** access to privileged NETWORK B **2823**.

The privileged network access information in the third row of PNAM database **3000** may include a PNet ID of NETB, MSN of DDDD00AB and LPAR access list with no entries. In other words, NETWORK B **2823** is a privileged network. In one embodiment, PNA tool **3300** may grant administered IHS **2809** access to privileged NETWORK B **2823**.

The privileged network access information in the fourth row of PNAM database **3000** may include a PNet ID of

NETC, MSN of 000AFA11 and LPAR access list of 07. In other words, NETWORK C **2823** is a privileged network. PNA tool **3300** may grant LPAR **2839-7** in PNA IHS **2804** access to privileged NETWORK C **2834**. PNA tool **330** may deny LPAR **2839-6** in PNA IHS **2804** access to privileged NETWORK C **2834**, even though LPAR **2839-6** is coupled to NETWORK C **2834** via network adapters **2830**, **2831**, **2832** and **2833**.

The privileged network access information in the fifth row of PNAM database **3000** may include a PNet ID of NETC, MSN of ACA000F1 and LPAR access list of 02. In other words, NETWORK C **2823** is a privileged network. PNA tool **3300** may grant LPAR **2842-2** in PNA IHS **2811** access to privileged NETWORK C **2834**. PNA tool **330** may deny LPAR **2842-1** in PNA IHS **2811** access to privileged NETWORK C **2834**, even though LPAR **2842-1** is coupled to NETWORK C **2834** via network adapters **2835**, **2836**, **2837** and **2838**.

FIG. 31 is a block diagram of a privileged network access (PNA) information handling system (IHS) **3100** that may be used in the disclosed PNA system. With respect to FIG. 11, like numbers indicate like elements. PNA IHS **3100** includes a processor **3105** that may include multiple cores. RNIC converging IHS **3100** processes, transfers, communicates, modifies, stores or otherwise handles information in digital form, analog form or other form. In one embodiment, PNA IHS **3100** includes a bus **3110**, i.e. channel **3110**. In another embodiment, bus **3110** may be multiple busses, i.e., multiple channels. Bus **3110** may couple processor **3105** to memory **3115** via a memory controller **3120** and memory bus **3125**. System memory **3115** may also be referred to as main memory. System memory **3115** may be a static random access memory (SRAM) array or a dynamic random access memory (DRAM) array. Processor **3105** may also include local memory such as L1, L2 and L3 caches.

In one embodiment, a video graphics controller **3130** couples display **3135** to bus **3110**. In another embodiment, PNA IHS **3100** may operate without display **3135** and/or video graphics controller **3130**. Nonvolatile storage **3140**, such as a hard disk drive, solid-state drive (SSD), CD drive, DVD drive, or other nonvolatile storage couples to bus **3110** to provide PNA IHS **3100** with permanent storage of information. System memory **3115** and nonvolatile storage **3140** are both forms of memory stores. In one embodiment, nonvolatile storage **3140** stores a hypervisor **3145** (HYPERVISOR) that governs operation of PNA IHS **3100**. In another embodiment, nonvolatile storage **3140** may store an operating system (not shown) that governs operation of PNA IHS **3100**. In another embodiment, nonvolatile storage **3140** may store an operating system (not shown) that governs operation of PNA IHS **3100**, where the operating system includes a hypervisor (not shown).

I/O devices **3150**, such as speakers, a keyboard and a pointing device, may couple to bus **3110** via I/O controller **3155** and I/O bus **3160**. One or more expansion busses **3165**, i.e. channels **3165**, such as USB, IEEE 1394 bus, ATA, SATA, PCI, PCIE, DVI, HDMI and other busses, i.e. channels, couple to bus **3110** to facilitate the connection of peripherals and devices to PNA IHS **3100**. Network interface controllers (NICs), for example, NIC **3170-1**, NIC **3170-2**, . . . , NIC **3170-G**, wherein G is the number of NICs, may couple to bus **3110** to enable PNA IHS **3100** to connect by wire or wirelessly to a network and other information handling systems. NIC **3170-1**, NIC **3170-2**, . . . , NIC **3170-G** may also be called a network communication adapter, network interface adapter, network adapter, network interface or an adapter. NIC **3170-1**, NIC **3170-2**, . . . , NIC **3170-G** may take many forms. For

example, NIC **3170-1**, NIC **3170-2**, . . . , NIC **3170-G** may take the form of an Ethernet (ETH) adapter, open systems adapter (OSA), RDMA enabled network interface controller (RNIC) or other network communication adapter.

While FIG. **31** shows one IHS that employs processor **3105**, the IHS may take many forms. For example, PNA IHS **3100** may take the form of a mainframe, server, central processor complex (CPC), desktop, portable, laptop, notebook, tablet or other form factor computer or data processing system. PNA IHS **3100** may take other form factors such as a gaming device, a personal digital assistant (PDA), a portable telephone device, a communication device or other devices that include a processor and memory.

PNA IHS **3100** includes a PNA tool computer program product **3300** on digital media **3175** such as a CD, DVD or other media. For simplicity, the term PNA tool will be used below. PNA IHS **3100** may store PNA tool **3300** in nonvolatile storage **3140** as PNA tool **3300'**. PNA IHS **3100** may also store hypervisor **3145** (HYPERVISOR) and logical partition (LPAR) **3180-1**, LPAR **3180-2**, . . . , LPAR **3180-F**, wherein **F** is the number of LPARs, in nonvolatile storage **3140**.

In another embodiment, PNA tool **3300'** may be part of the hypervisor **3145** (not shown). In another embodiment, PNA tool **3300'** may be in LPAR **3180-1**, LPAR **3180-2**, . . . , LPAR **3180-F**. In another embodiment, PNA IHS **3100** may store an operating system (not shown) that governs operation of PNA IHS **3100**, where the operating system includes a hypervisor (not shown) and where the operating system includes LPAR **3180-1**, LPAR **3180-2**, . . . , LPAR **3180-F** as virtual machines (not shown). When PNA IHS **3100** initializes, the IHS loads hypervisor **3145** into system memory **3115** for execution as hypervisor **3145'**. PNA IHS **3100** also loads PNA tool **3300'** into system memory **3115** for execution as PNA tool **3300''**. PNA IHS **3100** may also load LPAR **3180-1**, LPAR **3180-2**, . . . , LPAR **3180-F** into system memory **3115** for execution as LPAR **3180-1'**, LPAR **3180-2'**, . . . , LPAR **3180-F'**, respectively.

In another embodiment, when PNA IHS **3100** initializes, the IHS may load an operating system (not shown) into system memory **3115** for execution. In another embodiment, when PNA IHS **3100** initializes, the IHS may load an operating system (not shown) that includes a hypervisor (not shown) and includes LPAR **3180-1**, LPAR **3180-2**, . . . , LPAR **3180-F** as virtual machines (not shown) into system memory **3115** for execution.

FIG. **32** is a block diagram of a privileged network access management (PNAM) IHS **3200** that may be used in the disclosed privileged network access system. Like numbers indicate like elements with respect to FIG. **5**. PNAM IHS **3200** includes a processor **3205** that may include multiple cores. PNAM IHS **3200** processes, transfers, communicates, modifies, stores or otherwise handles information in digital form, analog form or other form. PNAM IHS **3200** includes a bus **3210** that couples processor **3205** to memory **3215** via a memory controller **3220** and memory bus **3225**. System memory **3215** may also be referred to as main memory. System memory **3215** may be a static random access memory (SRAM) array or a dynamic random access memory (DRAM) array. Processor **3205** may also include local memory such as L1, L2 and L3 caches. A video graphics controller **3230** couples display **3235** to bus **3210**. Nonvolatile storage **3240**, such as a hard disk drive, solid-state drive (SSD), CD drive, DVD drive, or other nonvolatile storage couples to bus **3210** to provide PNAM IHS **3200** with permanent storage of information. System memory **3215** and nonvolatile storage **3240** are both forms of memory stores. Nonvolatile storage **3240** stores an operating system **3245**

(OPERATING SYS) that governs operation of PNAM IHS **3200**. I/O devices **3250**, such as speakers, a keyboard and a pointing device, couple to bus **3210** via I/O controller **3255** and I/O bus **3260**.

One or more expansion busses **3265**, such as USB, IEEE 1394 bus, ATA, SATA, PCI, PCIE, DVI, HDMI and other busses, couple to bus **3210** to facilitate the connection of peripherals and devices to PNAM IHS **3200**. A network interface controller (NIC) **3270** couples to bus **3210** to enable PNAM IHS **3200** to connect by wire or wirelessly to a network and other information handling systems. NIC **3270** may also be called a network communication adapter, network interface adapter, network adapter, network interface or an adapter. NIC **3270** may take many forms. For example, NIC **3270** may take the form of an Ethernet (ETH) adapter, open systems adapter (OSA), RDMA enabled network interface controller (RNIC) or other network communication adapter.

While FIG. **32** shows one IHS that employs processor **3205**, the IHS may take many forms. For example, PNAM IHS **3200** may take the form of a desktop, portable, laptop, notebook, tablet or other form factor computer or data processing system. PNAM IHS **3200** may take other form factors such as a gaming device, a personal digital assistant (PDA), a portable telephone device, a communication device or other devices that include a processor and memory.

PNAM IHS **3200** includes a privileged network access management (PNAM) tool computer program product **3400** on digital media **3275** such as a CD, DVD or other media. For simplicity, the term PNAM tool will be used below. PNAM IHS **3200** may store PNAM tool **3400** in nonvolatile storage **3240** as PNAM tool **3400'**. PNAM IHS **3200** may also store operating system **3245** (OPERATING SYS) and PNAM database **3280** in nonvolatile storage **3240**. When PNAM IHS **3200** initializes, the IHS loads operating system **3245** into system memory **3215** for execution as operating system **3245'**. PNAM IHS **3200** also loads PNAM database **3280** and PNAM tool **3400'** into system memory **3215** for execution as PNAM database **3280'** and PNAM tool **3400''**, respectively.

FIG. **33** is a flowchart that shows a representative process flow of a privileged network access (PNA) tool **3300** that may be used in the disclosed privileged network access system. Process flow commences when PNA tool **3300** in PNA IHS **3100** initializes, as per block **3305**. If HCM tool **600** in HCM IHS **500** does not transmit HCM database **580**, as per decision block **3310**, process flow continues at decision block **3310**. If HCM tool **600** in HCM IHS **500** does transmit HCM database **580**, as per decision block **3310**, a hypervisor agent in PNA IHS **3100** may receive HCM database **580**, as per block **3315**. In one embodiment, the hypervisor agent in the PNA IHS **3100** is included in hypervisor **3145**.

The hypervisor agent may allow hypervisor **3145** to access HCM database **580**. Hypervisor **3145** may transmit HCM database **580** to PNA tool **3300**, as per block **3320**. PNA tool **3300** may extract the hardware configuration information of PNA IHS **3100** from the HCM database **580**, as per block **3325**. In one embodiment, the hardware configuration information of PNA IHS **3100** from HCM database **580** may include, but is not limited to, on a per adapter basis, machine serial numbers (MSNs), physical identifications (PIDs), logical identifications (LIDs), adapter types, a logical partition (LPAR) access list, a physical network identification (PNet ID) of the first port of the adapter and a PNet ID of the second port of the adapter. In one embodiment, the adapter type "0087" may be an OSA network adapter and the adapter type "0008" may be an RNIC network adapter.

In one embodiment, the PNA tool **3300** may share the extracted hardware configuration information of PNA IHS

3100 with hypervisor **3145**. Hypervisor **3145** may update the hardware configuration of PNA IHS **3100** with the extracted hardware configuration information of PNA IHS **3100**. In another embodiment, the PNA tool **3300** may share the extracted hardware configuration information of PNA IHS **3100** with LPARs **3180-1**, **3180-2**, . . . , **3180-F**, where F is the number of LPARs in PNA IHS **3100**. LPARs **3180-1**, **3180-2**, . . . , **3180-F** may update their respective hardware configuration with the extracted hardware configuration information of PNA IHS **3100**.

If PNAM tool **3400** in privileged network access management (PNAM) IHS **3200** does not transmit PNAM database **3280**, as per decision block **3330**, process flow continues at decision block **3330**. If PNAM tool **3400** in PNAM IHS **3200** does transmit PNAM database **3280**, as per decision block **3330**, a hypervisor agent in PNA IHS **3100** may receive PNAM database **3280**, as per block **3335**.

The hypervisor agent may allow hypervisor **3145** to access PNAM database **3280**. Hypervisor **3145** may transmit PNAM database **3280** to PNA tool **3300**, as per block **3340**. PNA tool **3300** may extract the privileged network access information of PNA IHS **3100** from the PNAM database **3280**, as per block **3345**. In one embodiment, the privileged network access information of PNA IHS **3100** from PNAM database **3280** may include, but is not limited to, on a per PNet ID, per IHS basis, PNet IDs, MSNs and logical partition (LPAR) access lists.

In one embodiment, the PNA tool **3300** may share the extracted privileged network access information of PNA IHS **3100** with hypervisor **3145**. Hypervisor **3145** may update the privileged network access information of PNA IHS **3100** with the extracted privileged network access information of PNA IHS **3100**. In another embodiment, the PNA tool **3300** may share the extracted privileged network access information of PNA IHS **3100** with LPARs **3180-1**, **3180-2**, . . . , **3180-F**, where F is the number of LPARs in PNA IHS **3100**. LPARs **3180-1**, **3180-2**, . . . , **3180-F** may update their respective privileged network access information with the extracted privileged network access information of PNA IHS **3100**.

Utilizing the extracted hardware configuration information and the extracted privileged network access information, PNA tool **3300** may determine if a particular LPAR is allowed to access a particular privileged network, as per decision block **3350**. PNA tool **3300** may determine that a particular LPAR is allowed to access a particular privileged network, as per decision block **3350**. PNA tool **3300** may grant the particular LPAR access to the particular privileged network, as per block **3355**.

For example, as shown in FIGS. **25A**, **25B** and **26**, LPAR **2529-7** in PNA IHS **2504** may attempt to access privileged NETWORK C **2524**. PNA tool **3300** may determine from the extracted hardware configuration information from HCM database **2600** that LPAR **2529-7** has access to network adapters **2522** and **2523** that both have a PNet ID of "NETC". PNA tool **3300** may determine from the extracted privileged network access information from PNAM database **2700** that PNet IDs "NETB" and "NETC" are the PNet IDs of privileged NETWORK B **2519** and privileged NETWORK C **2524**. PNA tool **3300** may determine from the extracted privileged network access information from PNAM database **2700** that LPAR **2529-4** and LPAR **2529-5** of PNA IHS **2504**, i.e. MSN 0CCC0AB2 are allowed to access privileged networks with a PNet ID of "NETB" and that LPAR **2529-7** of PNA IHS **2504** is allowed to access privileged networks with a PNet ID of "NETC". PNA tool **3300** may grant LPAR **2529-7** of PNA IHS **2504** access to privileged NETWORK C **2524**. Process flow terminates at end block **3365**.

PNA tool **3300** may determine that a particular LPAR is not allowed to access a particular privileged network, as per decision block **3350**. PNA tool **3300** may deny the particular LPAR access to the particular privileged network, as per block **3360**. For example, as shown in FIGS. **25A**, **25B** and **26**, LPAR **2529-7** in PNA IHS **2504** may attempt to access privileged NETWORK C **2524**. PNA tool **3300** may determine from the extracted hardware configuration information from HCM database **2600** that LPAR **2529-7** has access to network adapters **2522** and **2523** that both have a PNet ID of "NETC". PNA tool **3300** may determine from the extracted privileged network access information from PNAM database **2700** that PNet IDs "NETB" and "NETC" are the PNet IDs of privileged NETWORK B **2519** and privileged NETWORK C **2524**.

PNA tool **3300** may determine from the extracted privileged network access information from PNAM database **2700** that LPAR **2529-4** and LPAR **2529-5** of PNA IHS **2504**, i.e. MSN 0CCC0AB2 are allowed to access privileged networks with a PNet ID of "NETB" and that LPAR **2529-7** of PNA IHS **2504** is allowed to access privileged networks with a PNet ID of "NETC". PNA tool **3300** may grant LPAR **2529-7** of PNA IHS **2504** access to privileged NETWORK C **2524**. Process flow terminates at end block **3365**. Process flow terminates at end block **3365**. Alternatively, process flow may continue at start block **3305**.

FIG. **34** is a flowchart that shows a representative process flow of a privileged network access management (PNAM) tool **3400** that may be used in the disclosed privileged network access system. Process flow commences when PNAM tool **3400** in PNAM IHS **3200** is initialized, as per block **3405**. PNAM tool **3400** may determine if PNAM database **3280** exists in PNAM IHS **3200**, as per block **3410**. If PNAM database **3280** exists in PNAM IHS **3200**, PNAM tool **3400** opens PNAM database **3280** for modification, as per block **3415**. However, if PNAM database **3280** does not exist in PNAM IHS **3200**, PNAM tool **3400** generates a blank PNAM database **3280** in PNAM IHS **3200** and opens the PNAM database **3280** for modification, as per block **3420**.

PNAM database **3280** may store entries on a per privileged network, per PNA IHS basis, i.e., each row in PNAM database **3280** may contain information that pertains to the PNet ID of a particular privileged access network that couples to a particular PNA IHS, to which the particular PNA IHS may have access. Process flow continues as PNAM tool **3400** checks the PNA system for IHSs with access to privileged networks, as per block **3425**. If PNAM tool **3400** determines that the PNA system does not include PNA IHSs with access to privileged access networks, as per block **3425**, process flow terminates at end block **3460**.

If PNAM tool **3400** determines that the PNA system includes PNA IHSs with access to privileged access networks, PNAM tool **3400** may add the PNet IDs of the privileged access networks to which the PNA IHSs have privileged access, to PNAM database **3280**, as per block **3430**. For example, PNAM tool **3400** may add the PNet ID of "NETB" to PNAM database **3280** for privileged NETWORK B **2519**, to which PNA IHS **2504** has privileged access. In one embodiment, a user may input PNet IDs of physical networks to the PNAM tool **3400**. PNAM tool **3400** may then store the input PNet IDs of the physical networks in PNAM database **3280**, thereby listing the PNet IDs and respective physical networks as privileged access networks.

PNAM tool **3400** may modify rows of PNAM database **3280** to include the PNA IHSs and/or logical partition (LPAR) designations of LPARs in the particular PNA IHS that may access each particular network adapter, as per block

71

3435. For example, as shown in FIGS. 25A, 25B and 27, PNAM tool 3400 may modify the first row of PNAM database 2700, that has a "PNET ID" of "NET B" to include the "MSN" of PNA IHS 2504, "OCCCC0AB2" and the "LPAR ACCESS LIST" to include LPARs "04" and "05", thereby listing that LPAR 2529-4 and LPAR 2529-5 in PNA IHS 2504 may access privileged NETWORK B 2519. In one embodiment, a user may input LPAR designations of LPARs in particular PNA IHSs that may access particular privileged networks, to the PNAM tool 3400. The PNAM tool 3400 may then modify the rows of PNAM database 3280 to include the LPAR designations of LPARs in particular PNA IHSs that may access the particular privileged networks.

PNAM tool 3400 inspects the configuration of the PNA system that may include the PNet ID, MSN and LPAR access list on a per privileged network, per PNA IHS basis, as per block 3440. If PNAM tool 3400 determines that the PNA system configuration does not match PNAM database 3280, as per block 3440, PNAM tool 3400 updates the information stored in PNAM database 3280 with the inspected configuration of the PNA system, as per block 3445. In one embodiment, a user may view PNAM database 3280 with PNAM tool 3400 and determine if PNAM database 3280 matches the PNA system configuration. If PNAM database 3280 does not match the PNA system configuration, the user may input the PNA system configuration to the PNAM tool 3400. PNAM tool 3400 may store the PNA system configuration input by the user to PNAM database 3280.

If PNAM tool 3400 determines that the PNA system configuration does match PNAM database 3280, as per block 3440, process flow continues at block 3450. If PNAM tool 3400 determines that PNAM database 3280 has been modified and/or generated, as per block 3450, PNAM tool 3400 may transmit PNAM database 3280 to any or all PNA IHSs, as per block 3455. For example, as shown in FIGS. 25A and 25B, PNAM tool 3400 may transmit PNAM database 2700 to PNA IHS 2504, 2507, 2509 and/or 2511 via administrative network 2502. In one embodiment, a user may input or select a transmit command in PNAM tool 3400, causing PNAM tool 3400 to transmit PNAM database 3280 to any or all PNA IHSs. In another embodiment PNAM tool 3400 may transmit PNAM database 3280 to any or all PNA IHSs at a user specified time interval. If PNAM tool 3400 determines that the PNAM database 3280 has not been modified and/or generated, as per block 3450, process flow continues at block 3460. Process flow terminates at end block 3470. Alternatively, process flow may continue at start block 3405.

As will be appreciated by one skilled in the art, aspects of the disclosed methodology may be embodied as a system, method or computer program product. Accordingly, aspects of the present invention may take the form of an entirely hardware embodiment, an entirely software embodiment (including firmware, resident software, micro-code, etc.) or an embodiment combining software and hardware aspects that may all generally be referred to herein as a "circuit," "module" or "system." Furthermore, aspects of the present invention may take the form of a computer program product embodied in one or more computer readable medium(s) having computer readable program code embodied thereon.

Any combination of one or more computer readable medium(s) may be utilized. The computer readable medium may be a computer readable signal medium or a computer readable storage medium. A computer readable storage medium may be, for example, but not limited to, an electronic, magnetic, optical, electromagnetic, infrared, or semiconductor system, apparatus, or device, or any suitable combination of the foregoing. More specific examples (a non-exhaustive list)

72

of the computer readable storage medium would include the following: an electrical connection having one or more wires, a portable computer diskette, a hard disk, a random access memory (RAM), a read-only memory (ROM), an erasable programmable read-only memory (EPROM or Flash memory), an optical fiber, a portable compact disc read-only memory (CD-ROM), an optical storage device, a magnetic storage device, or any suitable combination of the foregoing. In the context of this document, a computer readable storage medium may be any tangible medium that can contain, or store a program for use by or in connection with an instruction execution system, apparatus, or device.

Computer program code for carrying out operations for aspects of the present invention may be written in any combination of one or more programming languages, including an object oriented programming language such as Java, Smalltalk, C++ or the like and conventional procedural programming languages, such as the "C" programming language or similar programming languages. The program code may execute entirely on the user's computer, partly on the user's computer, as a stand-alone software package, partly on the user's computer and partly on a remote computer or entirely on the remote computer or server. In the latter scenario, the remote computer may be connected to the user's computer through any type of network, including a local area network (LAN) or a wide area network (WAN), or the connection may be made to an external computer (for example, through the Internet using an Internet Service Provider).

Aspects of the present invention are described below with reference to flowchart illustrations and/or block diagrams of methods, apparatus (systems) and computer program products according to embodiments of the invention. It will be understood that each block of the FIGS. 6, 12, 18, 24, 33 and 34 flowchart illustrations and/or block diagrams, and combinations of blocks in the flowchart illustrations and/or block diagrams, can be implemented by computer program instructions. These computer program instructions may be provided to a processor of a general purpose computer, special purpose computer, or other programmable data processing apparatus to produce a machine, such that the instructions, which execute via the processor of the computer or other programmable data processing apparatus, create means for implementing the functions/acts specified in the flowchart of FIGS. 6, 12, 18, 24, 33 and 34 and/or block diagram block or blocks.

These computer program instructions may also be stored in a computer readable medium that can direct a computer, other programmable data processing apparatus, or other devices to function in a particular manner, such that the instructions stored in the computer readable medium produce an article of manufacture including instructions which implement the function/act specified in the flowchart and/or block diagram block or blocks.

The computer program instructions may also be loaded onto a computer, other programmable data processing apparatus, or other devices to cause a series of operational steps to be performed on the computer, other programmable apparatus or other devices to produce a computer implemented process such that the instructions which execute on the computer or other programmable apparatus provide processes for implementing the functions/acts specified in the flowchart of FIGS. 6, 12, 18, 24, 33 and 34 described above.

The flowchart of FIGS. 6, 12, 18, 24, 33 and 34 illustrate the architecture, functionality, and operation of possible implementations of systems, methods and computer program products that perform analysis in accordance with various embodiments of the present invention. In this regard, each block in the flowcharts of FIGS. 7 and 8 may represent a

module, segment, or portion of code, which comprises one or more executable instructions for implementing the specified logical function(s). It should also be noted that, in some alternative implementations, the functions noted in the block may occur out of the order noted in FIGS. 6, 12, 18, 24, 33 and 34. For example, two blocks shown in succession may, in fact, be executed substantially concurrently, or the blocks may sometimes be executed in the reverse order, depending upon the functionality involved. It will also be noted that each block of FIGS. 6, 12, 18, 24, 33 and 34 and combinations of blocks in the block diagrams and/or flowchart illustration, can be implemented by special purpose hardware-based systems that perform the specified functions or acts, or combinations of special purpose hardware and computer instructions.

The terminology used herein is for the purpose of describing particular embodiments only and is not intended to be limiting of the invention. As used herein, the singular forms “a”, “an” and “the” are intended to include the plural forms as well, unless the context clearly indicates otherwise. It will be further understood that the terms “comprises” and/or “comprising,” when used in this specification, specify the presence of stated features, integers, steps, operations, elements, and/or components, but do not preclude the presence or addition of one or more other features, integers, steps, operations, elements, components, and/or groups thereof.

The corresponding structures, materials, acts, and equivalents of all means or step plus function elements in the claims below are intended to include any structure, material, or act for performing the function in combination with other claimed elements as specifically claimed. The description of the present invention has been presented for purposes of illustration and description, but is not intended to be exhaustive or limited to the invention in the form disclosed. Many modifications and variations will be apparent to those of ordinary skill in the art without departing from the scope and spirit of the invention. The embodiment was chosen and described in order to best explain the principles of the invention and the practical application, and to enable others of ordinary skill in the art to understand the invention for various embodiments with various modifications as are suited to the particular use contemplated.

What is claimed is:

1. A bridging information handling system (IHS) comprising:

a processor;

a memory coupled to the processor, the memory including a hypervisor that is configured to:

receive from another IHS, via a network, an a hardware configuration manager (HCM) database that includes configuration information including physical network identifier (PNet IDs) entries and respective associated physical adapter type entries and respective associated logical partition (LPAR) access information entries;

transmit the HCM database to a bridging tool in the memory;

wherein the bridging tool extracts configuration information from the HCM database, the configuration information including PNet IDs entries and respective associated physical adapter type entries and respective associated logical partition (LPAR) access information entries, thus providing extracted physical bridging configuration information, wherein the extracted physical bridging configuration information identifies a given physical adapter of the bridging

IHS and indicates that the given physical adapter connects to a given physical network having a given PNet ID;

wherein the bridging tool extracts configuration information from the HCM database, the configuration information including PNet ID entries and respective associated virtual adapter ID entries and respective associated logical partition (LPAR) access information entries, thus providing extracted virtual bridging configuration information, wherein the extracted virtual bridging configuration information identifies a given virtual adapter of an LPAR executing within the bridging IHS and indicates that the given virtual adapter connects to the given physical network having the given PNet ID; and

wherein the bridging tool groups, on a per PNet ID basis, particular physical adapters from the extracted physical bridging configuration information sorted by PNet ID with particular virtual adapters from the extracted virtual bridging configuration information sorted by PNet ID;

a virtual switch within the hypervisor that the bridging tool employs to bridge a physical adapter in the bridging IHS and a virtual adapter in the bridging IHS that exhibit a same PNet ID, wherein the bridging tool configures the virtual switch to bridge the given physical adapter and the given virtual adapter such that the given virtual adapter connects to the given physical network via the virtual switch.

2. The bridging IHS of claim 1, wherein the bridging tool sorts, on a per PNet ID basis, the extracted physical bridging configuration information, thus providing extracted physical bridging configuration information sorted by PNet ID.

3. The bridging IHS of claim 1, wherein the bridging tool sorts, on a per PNet ID basis, the extracted virtual bridging configuration information, thus providing extracted virtual bridging configuration information sorted by PNet ID.

4. The bridging IHS of claim 1, wherein the virtual switch comprises the given physical adapter.

5. The bridging IHS of claim 1, wherein the given virtual adapter has an internal queued direct (IQD) communication adapter type.

6. The bridging IHS of claim 5, wherein the virtual switch comprises a bridge port connected to the given virtual adapter via an IQD communication network.

7. The bridging IHS of claim 1, wherein the given physical adapter has an open system adapter (OSA) adapter type.

8. A computer program product comprising a non-transitory computer readable storage medium having a computer readable program stored therein, wherein the computer readable program, when executed on a bridging information handling system (IHS), causes the bridging IHS to:

receive from another IHS, via a network, a hardware configuration manager (HCM) database that includes configuration information including physical network identifier (PNet IDs) entries and respective associated physical adapter type entries and respective associated logical partition (LPAR) access information entries;

transmit the HCM database to a bridging tool in the memory;

wherein the bridging tool extracts configuration information from the HCM database, the configuration information including PNet IDs entries and respective associated physical adapter type entries and respective associated logical partition (LPAR) access information entries, thus providing extracted physical bridging configuration information, wherein the extracted physical

75

bridging configuration information identifies a given physical adapter of the bridging IHS and indicates that the given physical adapter connects to a given physical network having a given PNet ID;

wherein the bridging tool extracts configuration information from the HCM database, the configuration information including PNet ID entries and respective associated virtual adapter ID entries and respective associated logical partition (LPAR) access information entries, thus providing extracted virtual bridging configuration information, wherein the extracted virtual bridging configuration information identifies a given virtual adapter of an LPAR executing within the bridging IHS and indicates that the given virtual adapter connects to the given physical network having the given PNet ID;

wherein the bridging tool groups, on a per PNet ID basis, particular physical adapters from the extracted physical bridging configuration information sorted by PNet ID with particular virtual adapters from the extracted virtual bridging configuration information sorted by PNet ID; and

a virtual switch within the hypervisor that the bridging tool employs to bridge a physical adapter in the bridging IHS and a virtual adapter in the bridging IHS that exhibit a same PNet ID, wherein the bridging tool configures the virtual switch to bridge the given physical adapter and

76

the given virtual adapter such that the given virtual adapter connects to the given physical network via the virtual switch.

9. The computer program product of claim 8, wherein the bridging tool sorts, on a per PNet ID basis, the extracted physical bridging configuration information, thus providing extracted physical bridging configuration information sorted by PNet ID.

10. The computer program product of claim 8, wherein the bridging tool sorts, on a per PNet ID basis, the extracted virtual bridging configuration information, thus providing extracted virtual bridging configuration information sorted by PNet ID.

11. The computer program product of claim 8, wherein the virtual switch comprises the given physical adapter.

12. The computer program product of claim 8, wherein the given virtual adapter has an internal queued direct (IQD) communication adapter type.

13. The computer program product of claim 12, wherein the virtual switch comprises a bridge port connected to the given virtual adapter via an IQD communication network.

14. The computer program product of claim 8, wherein the given physical adapter has an open system adapter (OSA) adapter type.

* * * * *